

















Manufacturer Information

for users regarding software updates (following the NAMUR recommendation 53)

1 Type of device

□ Field device / signal processing device

☐ Monitoring-/operation system / hand held terminal etc.

☐ Modem / interface

Manufacturer : Endress+Hauser GmbH+Co.KG

Device : Gammapilot M

Type : FMG60

Previous software version : V01.01.06 4...20mA HART

How can the previous software version number be identified:

(a) by standard HART Comando #0

(b) by ToF Tool

(c) by local operation FHX40 (Group selection-> system parameters

-> protocol+sw-no.
by FieldCare

2 Firmware/Software

New firm-/software version : V01.02.00 4...20mA HART

Description of the modification in comparison with the predecessor version:

(1) SIL2 for this software version for max. limit switch application

with 200 and 400 mm scintillator

3 Compatibility

Is the newly installed firmware/software compatible with the operating tools?

- - ToF Tool Field Tool Package version 4.04 or higher
 - HART Communicator DXR375
 - FHX40 (VU331)
 - FieldCare ab V 2.03.00 + DTM Library V 2.15.00
- ☐ No, description:





4

















Manufacturer Information

for users regarding software updates (following the NAMUR recommendation 53)

	FMG60	420mA HART	Instruction manual	BA236F/00/en/06.0					
	Device	Communication opti	ons Manual	Marking					
	Which 1	nanual corresponds to the new	firm-/software:						
	⊠ Yes □ No								
	Is a new	instruction manual necessary of	due to the modification of the f	irm-/software?					
	Instruc	tion manual							
	No, reasons: During EMC test −only in SIL mode- we recognize a small problem which we solve additional capacitors on the communication circuit board. For this reason a change hardware −Ex i− and Ex e circuit board- was necessary and is not compatible with t installed FMG60. If customer need an SIL2 upgrade for installed FMG60 200/400 mm max. limit sw please send back the device to PC Maulburg for modification. SIL2 hardware valid for Gammapilot M after 30. April 2007.								
		reasons:							
		/software update generally reco	ommended?						
J	O	ie ivalvior lecolililelidation 3.	,						
,	יי עווועעוווע		11						

Device	Communication optic	Marking			
FMG60	420mA HART	Instruction manual	BA236F/00/en/06.07 71041168		
FMG60	HART, PA, FF	Description of Instrument	BA287F/00/en/06.07		
FMG60		Functions	on ToF-Tool-CD		
11/1000		Functional safety manual	SD230F/00/en/05.07		
			No. 71041846		

The new instruction manuals can be referred in Internet: http://www.endress.com - area "DOWNLOAD" - declaration of the device and kind of manual

Price

						version?	

☐ Yes, new list price and update costs (without installation) are enclosed

No

