

Supplementary document

Liquiline Control CDC90

Fieldbus communication interface

Valid at:

Software version 01.00.00-0006

Document: Fieldbus communication interface

First edition 30 Mai, 2017

Current edition 11 September, 2017

SD01518C/07/EN/01.17
71383945

Author:

Endress+Hauser
Gesellschaft für Mess- und Regeltechnik mbH+Co. KG
Dieselstr. 24 70839
Gerlingen Germany

Table of contents

1	Note.....	6
1.1	About this manual.....	6
1.2	Abbreviations	6
2	Installation and wiring.....	7
3	Commissioning.....	8
3.1	Note.....	8
3.2	Reaction delay.....	8
3.3	Digital fieldbus to Device.....	8
3.4	Device to digital fieldbus.....	9
3.5	TCP IP Connectivity	9
3.6	Analog communication interface	9
4	General procedure	11
4.1	Code example to run a program from a PLS/DCS system.....	12
5	0/4...20 mA and digital IO command definition	13
5.1	Current input control	13
5.2	Digital input control	16
5.3	Example of procedural configuration with current output	18
6	Profibus DP server.....	20
6.1	Setting the device address	20
6.2	Configuration of the process data for PROFIBUS.....	20
6.2.1	GSD file.....	20
6.3	Output data modules	23
6.4	Data input modules.....	26
6.4.1	Media control unit alarm parameters	26
6.4.2	Program feedback parameters	27
6.4.3	Assembly signals.....	28
6.4.4	Transmitter measurement values	28
6.4.5	Sensor calibration and sensor information	29
6.4.6	Data mapping of the second channel resp. second measurement point	34
6.5	Example of procedural configuration with Profibus DP	34
7	Modbus TCP Server	37

7.1	Functional principle.....	37
7.1.1	General	37
7.2	Liquiline Control CDC90 integration via Modbus TCP	38
7.3	Command holding register data	38
7.3.1	Program control parameters	40
7.3.2	Limit parameters	41
7.4	Input register data.....	44
7.4.1	Media control unit alarm parameters	45
7.4.2	Program feedback parameters	46
7.4.3	Assembly signals.....	47
7.4.4	Transmitter measurement values	47
7.4.5	Sensor calibration and sensor information	48
7.4.6	Media control unit and program parameters.....	52
7.5	Example of procedural configuration with Modbus TCP Master	54
8	Ethernet IP data connection.....	57
8.1	Network settings	57
8.2	Integration into a control system	57
8.2.1	EDS file	57
8.3	Input data	57
8.3.1	Program control parameters	58
8.4	Output data.....	59
8.4.1	Media control unit alarm parameters.....	59
8.4.2	Program feedback parameters.....	60
8.4.3	Transmitter measurement values.....	61
8.4.4	Sensor calibration and sensor information	62
8.4.5	Media control unit and program parameters.....	67
8.5	Example of procedural configuration with Ethernet IP	68
9	Profinet data connection.....	71
9.1	Setting the device address	71
9.2	Configuration of the process data for PROFINET IO	72
9.3	Integration into a control system	72
9.3.1	GSDML file	72
9.4	Input data	73

9.4.1	Program control parameters	74
9.5	Output data.....	75
9.5.1	Media control unit alarm parameters.....	75
9.5.2	Program feedback parameters.....	76
9.5.3	Transmitter measurement values.....	77
9.5.4	Sensor calibration and sensor information	78
9.5.5	Media control unit and program parameters.....	83
9.6	Example of procedural configuration with Profinet IO	85
10	OPC UA Connection and data	87
10.1	Read/Write data.....	87
10.1.1	Program control parameters	87
10.1.2	Limit parameters	88
10.2	Read only data	90
10.2.1	Media control unit alarm parameters	90
10.2.2	Program feedback parameters	91
10.2.3	Assembly signals.....	91
10.2.4	Transmitter measurement values	91
10.2.5	Sensor calibration and sensor information	92
10.2.6	Media control unit and program parameters.....	94
10.2.7	Data mapping of the second channel resp. second measurement point	95
10.3	Example of procedural configuration with OPC UA	95
11	Default possible program.....	99
11.1	Cleaning and flush programs.....	99
11.1.1	Cleaning and flush program with sensor staying in service position	99
11.1.2	Cleaning and flush program with sensor back to measurement position	101
11.1.3	Flush or cleaning programs for application with short and fixed meas. interval 104	
11.1.4	Flush and cleaning programs for application with long and fixed interval.....	107
11.2	Programs pH glass and pH Isfet calibration.....	108
11.2.1	Validation buffer 1 program with sensor staying in service position	108
11.2.2	Validation buffer 1 program with sensor back to measurement position	109
11.2.3	Validation buffer 2 program with sensor staying in service position	112
11.2.4	Validation buffer 2 program with sensor back to measurement position	113

11.2.5	2 Pt verification program with sensor staying in service position	116
11.2.6	2 Pt verification program with sensor back to measurement position	118
11.2.7	2 Pt adjustment program with sensor staying in service position	121
11.2.8	2 Pt adjustment program with sensor back to measurement position	124
11.3	Parking and regeneration pH glass and pH Isfet	127
11.4	Programs pH ORP calibration	128
11.5	Program with Hold function	132

1 Note

1.1 About this manual

This supplementary document must only be used in conjunction with a field device Liquiline Control CDC90 current output, Modbus TCP, Profibus, Ethernet IP and Profinet.

This supplementary document is an integral part of the Operating Instruction and extends it with additional information for use with current output, Modbus TCP, Profibus, Ethernet IP and Profinet.

Additional information is contained in the Liquiline Control CDC90 user manual.

This document is aimed at individuals who are integrating the device into a current output Modbus TCP, Profibus, Ethernet IP and Profinet network. It is assumed that the reader has fundamental knowledge of current output, Modbus TCP, Profibus, Ethernet IP and Profinet technology.

1.2 Abbreviations

n.a. Not applicable

NaN Not a Number (IEEE-754, 7Fh A0h 00h 00h)

ENP Electronic name plate

AI Analog Input (PA Profile function block)

DI Discrete Input (PA Profile function block)

AO Analog Output (PA Profile function block)

DO Discrete Output (PA Profile function block)

2 Installation and wiring

Installation and wiring is described in the operating instructions of Liquiline Control CDC90.

3 Commissioning

3.1 Note


The device starts when the supply voltage is applied. This process can take up to two minutes depending on the device's configuration. Fieldbus communication with the device is not possible during the start-up process.

When the fieldbus interface is ready for operation, it is signaled by the (blinking green) PWR LED on all connected Ethernet switch ports. This occurs, at the very latest, 30 seconds after the measuring screen has been displayed.

 Several fieldbus communications can run simultaneously, but only one is used to send commands to the Liquiline control CDC90.

To activate which fieldbus communication interface is used to send command, navigate to:

Menu/Setup/System settings/Communication/Fieldbus communication



1. Pic. Multiple fieldbus communication with Modbus TCP connection as command interface

3.2 Reaction delay

The reaction delay is different depending on the direction of the data flow.

3.3 Digital fieldbus to Device

The physical interface to the customer's central control system (PLS or DCS) is the Ethernet switch mounted on the CDC90. The connection on CDC90 side is done via an Ethernet cable with a M12 connector, the other cable end depends on PLS/DCS interface port. It can be RJ45 or M12. Received data is sent without delay to the internal component demanding this data. The internal components have a fixed sampling rate of 3 Hz.

	RJ45	Standard cable	Industrial normed cable	M12
	2	OR TxD-	OR	3
	1	OR/WH TxD+	YE	1
	6	GN RxD-	BU	4
	3	GN/WH RxD+	WH	2

1. Pic. Ethernet switch and Cable connector configuration

3.4 Device to digital fieldbus


The reaction delay is defined as the time span between the moment a process value assumes a new value and this value is replied to the fieldbus client.

$$T_{\text{Reaction delay}} = T_{\text{Sensor response time}} + T_{\text{Sensor sampling time}} + T_{\text{Modbus response time}}$$

3.5 TCP IP Connectivity

 Via the TCP port 502 and a standard IP address 192.168.0.1, you can support up to 3 parallel TCP connections with the device simultaneously. Only one connection is the master by sending commands resp. writing parameters to the CDC90.

To change the IP address, navigate to Menu/System setting/Communication/Transmitter connection and change the **IPC address**. The IP address (ADDR1 . ADDR2 . ADDR3 . ADDR4) of the transmitter will change automatically to ADDR4 + 3. The IP transmitter address can be changed later.



Setup/System settings/Communication CH:1					
Gateway	Select				
CM44 IP	192	168	0	4	502
Mask	255	255	255	0	
Gateway	0	0	0	0	
IPC address	192	168	0	1	502


Close **Finish** ✓

2. Pic. IP address configuration visualization

 Changing the transmitter Modbus IO configuration will lead to information loss and software instability. It is recommended to leave any IO configuration (AI, AO, DI and DO of CM44), these connectivities are responsible for the transfer of data between the transmitter and the CDC90 controller such as measurement values, calibration values and pump canister status.


3.6 Analog communication interface

The analog communication is done via the analog input and output reserved in the transmitter. For the measurement value use the 4 AO module.




3. Pic. Current output module reserved for measurement values

The configuration of the measurement output interface can be done on transmitter webserver. The default transmitter IP address is 192.168.0.4. Start your browser and enter the transmitter IP address. If a password is required enter as user admin and password admin. Navigate to Setup/Output and select the output 7.1 to 7.4 and follow the displayed configuration requirements.



4. Pic. Example of current output configuration on pH meas. value

To send command to CDC90, use the analog input port (second port) reserved therefore.



5. Pic. Analog input port to send command to CDC90 (left) and output to get status response from CDC90 (right)

4 General procedure

The CDC90 has a fieldbus communication interface. This offers the possibility to start and stop programs, to change the operating mode configuration and to monitor the system such as measurement values, actor state, transmitter and sensors information.

The procedure which can be used to control the system via PLS respectively DCS has for example the following steps:

1. Stop a measurement loop
2. Start a cleaning program (for example **program 1: Cleaning**)
3. Start a verification program (for example verification of buffer 7 and buffer 4: **program 5: 2 Pt verification**. Or a verification on one point buffer 4 or buffer 7: Program 4: **Valid. Buffer 4** or Program 3: **Valid. Buffer 7**)
4. The PLS resp. DCS will compare the calibration data (for example for pH glass sensor: slope, zero point, mV meas. values) with the value defined from service department or SOP and decides if an adjustment should be done or not: Per default CDC90 compares the calibration result (Offset, zero point, operating point, slope delta zero point, delta operating point and delta slope) and gives an alarm. If one of these alarms is detected the system will stop and wait for a command. **The advantage is to get an alarm before adjusting the sensor and not after.**
5. For an **adjustment on site** with the CDC90 control, start the program (for example **program 7: 2 Pt adjustment**). For an adjustment in laboratory set the **operating mode on 5 permanently (maintenance assembly mode) to permit the change of the sensor and run the sensor adjustment in the laboratory.**
6. **Park the sensor** if necessary (if the next measurement loop must not start the next few days) by starting the **program 6: Regeneration** for example. If the sensor is getting old (very long response time after cleaning, for example) regeneration can help to extend the sensor's life.
7. Send the **sensor to measurement position** by starting the **program 9: Meas** if the next measurement must be started.



To achieve such a procedure the customer control system, should set constantly the parameter "**Enable DCS/PLS**" to 1. This determines that the control system is taking the control of the Liquiline control CDC90 system. If an alarm appears during the verification procedure it is recommended to start a new cleaning procedure via PLS and restart the verification.



The CDC90 stores only successful validation resp. calibration data to the sensors. This procedure is done to avoid warnings or alarms after the sensor adjustment in the process. A verification resp. calibration or sensor adjustment is strongly depending on the calibration result ranges. To define the calibration result ranges, navigate to **MENU/SETUP/Settings/Next**

4.1 Code example to run a program from a PLS/DCS system

```

General_ProgramNr: BYTE; //Selected program number: Input 1
DCSOperatingMode: BYTE; //Operating mode: Input 2
General_Start: BYTE; //Program start/stop: Input 3
General_Prg_Release_PRG_ERROR: BYTE; //Command when a program error occurred: Input 4
FieldOrDCSContrl: BYTE; // Enable DCS/PLS control: Input 5
SelectChannelNr: BYTE; //Channel selection: Input 6
Program1ReadyForStart: BYTE; //Program ready to run: Output 17
Program1Abort: BYTE; //Program abort: Output 18
OperatingMode: BYTE; //Operating mode: Output 13
ControlStatus: USINT; //0= No program started, 1= Program started
CASE ControlStatus OF
0://Start a program
  IF OperatingMode <> 4 AND OperatingMode <> 5 THEN //(Service mode or Assembly maintenance); The command won't
be accept from the system
    IF Program1ReadyForStart THEN
      SelectChannelNr:= 1; //For channel 1
      FieldOrDCSContrl:= 1;
      DCSOperatingMode:= 3; //PLS DCS mode
      General_ProgramNr:= xxx; //xxx [1..10] is the program number which should start
      General_Start:= 1; //Start the program xxx
    END_IF
    IF Program1ReadyForStart = FALSE THEN
      ControlStatus:= 1;
    END_IF
  END_IF
1://Observe the running program
  General_Start:= 2; //Leave the system to stop program at the last step
  IF Program1Abort THEN //Check for error during the running time
    General_Prg_Release_PRG_ERROR:= .... //What do you want to do:1= Restart last program step; 2= Start next
program step; 3= Stop / Abort program;4= Restart program
    //For a calibration or adjustment program, please set it to 4 (restart program or 3 Stop
  END_IF
  IF Program1ReadyForStart AND ... (other conditions depending of your plant) THEN
    ControlStatus:= 0;
  END_IF
END_CASE

```

5 0/4...20 mA and digital IO command definition

5.1 Current input control

The control of Liquiline Control CDC90 with current is simply done by the current input and output interface of the CM44 module installed on board.

 Please use the current output 2 on the Base E (CPU of CM44) to read each response of the automation system and use the reserved current input 2 (additional module installed AI pin 23+ 24-) to send the commands from the PLS respectively DCS to control the automation system. Please read the user manual for more information about the current input and output module.

The commands accepted from the Liquiline Control CDC90 are simply current in mA with a tolerance of **+/-0.2 mA**. The CDC90 starts to analyze each current which stays stable for a certain amount of time: more than **4 seconds**. The response of each command is sent as current from Liquiline Control CDC90. The following table shows all available commands and responses to control the Liquiline Control CDC90.

 System states or warnings such as canister empty, no sensor communication, glass break or calibration error are all summarized in a single error response signal: 22mA. When all commands and procedures are working without error, the response of the CDC90 controller is different to 22 mA. **To get more system states use the external digital out explained in the next chapter.**

In addition the current output module with four outputs is reserved to transfer the measurement values such as pH and temperature. The configuration of these outputs is done as mentioned in the CM44 manual. This gives a flexibility to transfer any signals that are important for the customer control system.

 The number of outputs for measurement signals is limited to four. The output interface can be configured individually via Webserver. Please read the CM44x manual for more information.

Customer control system Command[mA]	Command explanation	CDC90 Answer [mA]	Answer explanation
+/-0.2mA			
PLS 0..20mA PLS Config.			
0	Stop the CDC90 control from PLS, this stops automatically a running program.	0	System stopped
1	Customer control system takes control of CDC90 through current input, no command from field device is accepted	1	PLS control set
2	Select channel resp. meas. point 1 for the configuration; after the answer, this current can be switched to another channel	2	Channel 1 for configuration seleted
3	Select channel resp. meas. point 2 for the configuration; after the answer, this current can be switched to another channel	3	Channel 2 for configuration seleted
4	Set operating mode to automatic	4	System set to automatic mode
PLS 4..20mA PLS Config.			
4	Stop the CDC90 control from PLS, this stops automatically a running program	4	System stopped
5	Customer control system takes control of CDC90 through current input, no command from field device is accepted	5	PLS control set
6	Select channel resp. meas. point 1 for the configuration; after the answer, this current can be switched to another channel	6	Channel 1 for configuration seleted
7	Select channel resp. meas. point 2 for the configuration; after the answer, this current can be switched to another channel	7	Channel 2 for configuration seleted
8	Set operating mode to automatic	8	System set to automatic mode


Program execution			
	No program running	4	No program running
11	Run program 1	11	Program 1 is running
12	Run program 2	12	Program 2 is running
13	Run program 3	13	Program 3 is running
14	Run program 4	14	Program 4 is running
15	Run program 5	15	Program 5 is running
16	Run program 6	16	Program 6 is running
17	Run program 7	17	Program 7 is running
18	Run program 8	18	Program 8 is running
19	Run program 9	19	Program 9 is running
20	Run program 10	20	Program 10 is running
		22	Alarm occurred
21	Idle	NONE	The current running program will stop automatically at the end
Command in case of error		Error handling	
9	Restart whole program		
10	Jump to next program step		

i For a multi-channel Liquiline Control CDC90, please use the current 6 mA resp. 2 mA (switch to measurement point 1) and 7 mA resp. 3 mA (switch to measurement point 2) to send commands to control the respective measurement point.

5.2 Digital input control

The CDC90 is equipped with an external remote IO. This can be used to send commands to the CDC90 and receive states related to hardware and programs. To use the digital input and output a setting should be done. Navigate to:

Menu/Setup/System settings/Remote control/Next/Next




6. Pic. Softkeys resp. digital in and output configuration screens

The menu is used to link the softkeys (1 left, 2 second left, 3 third left and 4 right) to programs as well external digital input (13, 14, 15 and 16) to programs. Set the program which should be triggered by pressing the Softkey 1 or by switching on the digital input 13, set the program which should be triggered by pressing the Softkey 2 or by switching on the digital input 14, set the program which should be triggered by pressing the Softkey 3 or by switching on the digital input 15 and set the program which should be triggered by pressing the Softkey 4 or by switching on the digital input 16. By setting the program you can also set which channel should be selected for executing the program. This feature is suitable for users who do not want to use the touch screen to switch the channel before pressing a Softkey.

To switch on the digital input connectivity press “Next” and switch on the two boxes “Used digital input” (gives the possibility to send commands via digital input) and “Used digital out” (gives the possibility to receive system states via digital output).



For a multi-channel system, the settings should be done for each channel. Press the symbol CH: 1 on top of the screen Setup/System settings/Softkey and select the next channel.



The following table shows the system states sent via digital out of the remote IO.

Digital output	Status	Description
13	Blinking (0 and 24 V)	1. Operating mode of channel 1 is on Service 2. Operating mode of channel 1 is on Maintenance 3. The assembly position of channel 1 is not defined, level switches are defective or the assembly is stuck
13	24 V	Assembly on channel 1 is in measurement position
13	0 V	Assembly on channel 1 is in service position
14	Blinking (0 and 24 V)	1. Operating mode of channel 2 is on Service 2. Operating mode of channel 2 is on Maintenance. 3. The assembly position of channel 2 is not defined, level switches are defective or the assembly is stuck
14	24 V	Assembly on channel 2 is in measurement position
14	0 V	Assembly on channel 2 is in service position
15	24 V	A program is running (on channel 1 or 2)
15	0 V	No program is running (on channel 1 and 2)

16	24 V	System failure, warning or assembly on maintenance
16	0 V	No alarm

5.3 Example of procedural configuration with current output

Start **program 9** on measurement point 1 from PLS respectively DCS with current out **0...20 mA**.

Id		Current values [mA]	Description
1	Command	1 mA	Take control of the Liquiline CDC90 from customer control system
	Answer	1 mA	Answer that the command was received and registered
2	Command	2 mA	Switch all commands to control measurement point 1
	Answer	2 mA	Answer that the command was received and registered
3	Command	19 mA	Start program 9
	Answer	19 mA	Answer that the program 9 is running
4	Command	21 mA	The program will stop automatically at the end and wait for next the command
	Answer	19 mA	

Start **program 9** on measurement point 2 from PLS respectively DCS with current out **4...20 mA**.

Id		Current values [mA] Hold 4 seconds	Description
1	Command	5 mA	Take control of the Liquiline CDC90 from customer control system
	Answer	5 mA	Answer that the command was received and registered
2	Command	6 mA	Switch all commands to control measurement point 1
	Answer	6 mA	Answer that the command was received and registered
3	Command	19 mA	Start program 9


	Answer	19 mA	Answer that the program 9 is running
4	Command	21 mA	The program will stop automatically at the end and wait for next the command
	Answer	19 mA	

 Send 21 mA after starting a program to ensure that the program will stop automatically at the end. If this current information is not sent, the program will run continually after the end and can be stopped manually by sending another current command such as 0 mA, 3 mA or another program trigger.

 If an error occurs, the Liquiline Control CDC90 will send a response signal 22 mA. The field device diagnosis interface contains all details about the error occurred.

6 Profibus DP server

The data transfer to a PLS or DCS is done via a gateway (Modbus TCP/ Profibus DP). To connect the customer control system to CDC90, the customer control system must be connected to the gateway first. **For special project, we use different controller which allows a direct connection without gateway.**



7. Pic. Gateway connection with CDC90 Ethernet switch



Please read the installation manual of the gateway enclosed to the Liquiline Control CDC90.

6.1 Setting the device address

The default Profibus address is 77. To change the device address, please read the manual of the gateway. For a two measurement points resp. channels system, the IP address of the second gateway must be set to 192.168.0.6. This is defined as the gateway controlling the second measurement point.



8. Pic. IP address configuration two channel (CH1: 192.168.0.5 and CH1: 192.168.0.6)

6.2 Configuration of the process data for PROFIBUS



6.2.1 GSD file

The electronic data sheet (GSD) file can be obtained from the following sources:

<https://www.endress.com/en/Field-instruments-overview/liquid-analysis-product-overview/pH-sensor-automatic-cleaning-calibration-cdc90>

Upload the GSD file "HMSB1831" to the PLS resp. DCS system. Insert data output module (2 words and 4 words) and data input module (8 words, 32 words and 64 words).

 For a multichannel system please set the Profibus address of the second gateway as described in the gateway user manual. The default address of both modules is 5.



1. Pic. Representation of the data container of the gateway on Siemens TIA portal and Simatic

The input and output data modules are mapped on the following chapters.

 To write the parameters, the PLS resp. DCS must set constantly the parameter (**Enable DCS/PLS control see table below**).

 Constantly writing this parameter means take the control of the CDC90, no commands of the field device are accepted anymore. Setting this parameter to zero does not give the PLS resp. DCS the possibility to write parameters or control the CDC90 anymore.

6.3 Output data modules

The output data modules are used as command parameter, to configure and start programs of the CDC90.

 **Real** and **DWORD** parameters must be swapped on Siemens and Schneider control systems. We consider that a float value is built with the following format bytes AB CD, the swap function results in CD BA. Please note that these two systems are the ones validated from our system integration.

 Take control of Liquiline Control CDC90 from PLS resp. DCS means: Permanently set the parameter determining the control from PLS "**Enable DCS/PLS**" to 1 (see the following description). During that time, it is not possible to set or configure any parameter from the field device. If this parameter is set back to zero, the CDC90 will stop program running at its last step. The field device is then free to be configured.

Write/Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Profibus address	Bytes	Unit
Selected program number Range: 1-10	General_ProgramNr	BYTE	WORD	2	1	1, 2	NONE
Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS DCS mode, 4 = Service mode, 5 = Assembly maintenance	DCSOperatingMode	BYTE	WORD	2	2	3, 4	NONE
Program start/stop 1= Start selected program 0= Stop program 2= Stop automatically after starting (without closing the connection to PLS)	General_Start	BOOL	WORD	2	3	4, 6	NONE
Command when a program error occurred 1= Restart last program step 2= Start next program step 3= Stop / Abort program 4= Restart program	General_Prg_Release_PR G_ERROR	BYTE	WORD	2	4	7, 8	NONE
Enable DCS/PLS control	FieldOrDCSContrl	BOOL	WORD	2	5	8, 10	NONE
Channel selection [1..2]	SelectChannelNr	USINT	WORD	2	6	11, 12	NONE

6.4 Data input modules

The data container of this block includes status, alarms, warnings, measurement values, calibration data and device information.

6.4.1 Media control unit alarm parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Profibus address	Bytes	Unit
Canister 2 nearly empty	CanisterLevel2_1Warning	BOOL	WORD	2	1	1, 2	NONE
Pump 2 active	Pump2On	BOOL	WORD	2	2	3, 4	NONE
Canister 3 nearly empty	CanisterLevel3_1Warning	BOOL	WORD	2	3	5, 6	NONE
Pump 3 active	Pump3On	BOOL	WORD	2	4	7, 8	NONE
Canister 1 nearly empty	CanisterLevel1_1Warning	BYTE	WORD	2	5	9, 10	NONE
Pump 1 active	Pump1On	BOOL	WORD	2	6	11, 12	NONE
Air pressure measured	PressureSwitchAirIn	BOOL	WORD	2	7	13, 14	NONE
Communication error between controller and pilot valve block	CommErrorPilotValveBufferProvider	BOOL	WORD	2	8	15,16	NONE
Communication error between controller and remote IO	CommErrorRemoteIOBufferProvider	BOOL	WORD	2	9	17, 18	NONE

Canister 2 empty	FeedbackFillLevel2_1_Empty	BOOL	WORD	2	10	19, 20	NONE
Canister 3 empty	FeedbackFillLevel3_1_Empty	BOOL	WORD	2	11	21, 22	NONE
Canister 1 empty	FeedbackFillLevel1_1_Empty	BOOL	WORD	2	12	23, 24	NONE

6.4.2 Program feedback parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Profibus address	Bytes	Unit
Operating mode	OperatingMode	BYTE	WORD	2	13	25, 26	NONE
Selected program	SelectedProgramm	BYTE	WORD	2	14	27, 28	NONE
Time left till program step end	CurrentStepTime	INT	WORD	2	15	29, 30	Seconds
Current program step number	Program1CurrentStep	INT	WORD	2	16	31, 32	NONE
Program ready to run	Program1ReadyForStart	BOOL	WORD	2	17	33, 34	NONE
Program abort	Program1Abort	BOOL	WORD	2	18	35, 36	NONE
Program ended	Program1Ended	BOOL	WORD	2	19	37, 38	NONE

Error code during the execution of the program	ErrorNumber	UINT	WORD	2	20	39, 40	NONE
--	-------------	------	------	---	----	--------	------

6.4.3 Assembly signals

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Profibus address	Bytes	Unit
Assembly in service position	AssemblyServicePosition	BOOL	WORD	2	21	41, 42	NONE
Assembly in meas. Position	AssemblyMeasPosition	BOOL	WORD	2	22	43, 44	NONE
Provide air pressure	ProvidedPressure	BOOL	WORD	2	23	45, 46	NONE

6.4.4 Transmitter measurement values

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Profibus address	Bytes	Unit
Alarm transmitter CM42	CM42_ALM_CODE	INT	WORD	2	24	47, 48	NONE
pH value	pHValue	REAL	2xWORD	4	25	49, 50, 51, 52	pH
State pH value	pH_State	BYTE	WORD	2	27	53, 54	NONE

mV value	mV_Value	REAL	2xWORD	4	28	55, 56, 57, 58	mV
State mV value	mV_State	BYTE	WORD	2	30	59, 60	NONE
Impedance value	GlassImp	REAL	2xWORD	4	31	61, 62, 63, 64	Mega Ohm
State impedance value	GlassImp_State	BYTE	WORD	2	33	65, 66	NONE
Temperature value	MeasTemperature	REAL	2xWORD	4	34	67, 68, 69, 70	°C
State temperature value	Temperature_State	BYTE	WORD	2	36	71, 72	NONE
Alarm critic Liquiline	Transmitter_Sum_Alm	BOOL	WORD	2	37	73, 74	NONE
Alarm transmitter CM44	Transmitter_Sum_Warn	BOOL	WORD	2	38	75, 76	NONE
Alarm Impedance	Transmitter_GlasAlarm	BOOL	WORD	2	39	77, 78	NONE
Alarm glass	Transmitter_Glasbruch	BOOL	WORD	2	40	79, 80	NONE

6.4.5 Sensor calibration and sensor information

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Profibus address	Bytes	Unit
Alarm zero point	ZeroPointOutOfRange	BOOL	WORD	2	41	81, 82	NONE
Alarm slope	SlopeOutOfRange	BOOL	WORD	2	42	83, 84	NONE
Alarm delta zero point	DeltaZeroPointOutOfRange	BOOL	WORD	2	43	85, 86	NONE
Alarm delta slope	DeltaSlopeOutOfRange	BOOL	WORD	2	44	87, 88	NONE
pH unstable during calibration	Transmitter_pH_Instabil	BOOL	WORD	2	45	89, 90	NONE
Remote communication error	Transmitter_Remote_Cal_Abort	BOOL	WORD	2	46	91, 92	NONE
Zero point	ZeroPoint	REAL	2xWORD	4	47	93, 94, 95, 96	pH
Slope	Slope	REAL	2xWORD	4	49	97, 98, 99, 100	pH/mV
Delta Zero point	DeltaZeroPoint	REAL	2xWORD	4	51	101, 102, 103, 104	pH
Delta Slope	DeltaSlope	REAL	2xWORD	4	53	105, 106, 107, 108	pH/mV

Max. meas. Temperature	MaxTemp	REAL	2xWORD	4	55	109, 110, 111, 112s	°C
operating time sensor	OpHours	REAL	2xWORD	4	57	113, 114, 115, 116	Hours
Number of sensor adjustment	NumCalibration	INT	WORD	2	59	117, 118	NONE
Adjustment type	ADJ_CAL	BYTE	WORD	2	60	119, 120	NONE
Adjustment date	Adjustement_Date	DATE	DWORD	4	61	121, 122, 123, 124	SINCE 01.01.197 0, 00:00; YYYY-MM- DD HH:MM:SS
Adjusted zero point	Adjustement_ZeroPoint	REAL	2xWORD	4	63	125, 126, 127, 128	pH
Adjusted slope	Adjustement_Slope	REAL	2xWORD	4	65	129, 130, 131, 132	pH/mV
pH Meas. Value in buffer 7	Adjustement_pH1	REAL	2xWORD	4	67	133, 134, 135, 136	pH
mV Meas. Value in buffer 7	Adjustement_mV1	REAL	2xWORD	4	69	137, 138,	mV

							139, 140	
Meas. temperature Value in buffer 7	Adjustement_Temperatur1	REAL	2xWORD	4	71	141, 142,	°C	
						143, 144		
SCS meas. Value 1	Adjustement_SCS1	REAL	2xWORD	4	73	145, 146,	Mega Ohm	
						147, 148		
Response time till stability 1	Adjustement_ResponseTime1	INT	WORD	2	75	149, 150	Seconds	
mV value 1 after 30 s	Adjustement_mV_T30_1	REAL	2xWORD	4	76	151, 152	Seconds	
						153, 154		
pH Meas. Value in buffer 4	Adjustement_pH2	REAL	2xWORD	4	78	155, 156,	pH	
						157, 158		
mV Meas. Value in buffer 4	Adjustement_mV2	REAL	2xWORD	4	80	159, 160,	mV	
						161, 162		
Meas. temperature Value in buffer 4	Adjustement_Temperatur2	REAL	2xWORD	4	82	163, 164,	°C	
						165, 166		
SCS meas. Value 2	Adjustement_SCS2	REAL	2xWORD	4	84	167, 168,	Mega Ohm	
						169, 170		

Response time till stability 2	Adjustement_ResponseTime2	INT	WORD	2	86	171, 172	Seconds
mV value 2 after 30 s	Adjustement_mV_T30_2	REAL	2xWORD	4	87	173, 174, 175, 176	Seconds
Operating point	OperatingPoint	REAL	2xWORD	4	89	177, 178, 179, 180	mV
Delta operating point	DeltaOperatingPoint	REAL	2xWORD	4	91	181, 182, 183, 184	mV
Adjusted operating point	Adjustement_OperatingPoint	REAL	2xWORD	4	93	185, 186, 187, 188	mV
Reference impedance 1	Adjustement_RefImpedance1	REAL	2xWORD	4	95	189, 190, 191, 192	MOhm
Reference impedance 2	Adjustement_RefImpedance2	REAL	2xWORD	4	97	193, 194, 195, 196	MOhm
pH Offset	pHOffsetValue	REAL	2xWORD	4	99	197, 198, 199, 200	pH
Offset pH out of limit	pHOffsetOutOfRange	BOOL	WORD	2	101	201, 202	NONE
Operation point out of limit	OperationPointOutOfRange	BOOL	WORD	2	102	203, 204	NONE

Delta Operation point out of limit	DeltaOperationPointOutOfRange	BOOL	WORD	2	103	205, 206	NONE
Temperature offset out of limit	TempOffsetOutOfRange	BOOL	WORD	2	104	207, 208	NONE

6.4.6 Data mapping of the second channel resp. second measurement point

The second measurement point is controlled via a second gateway. The data mapping is the same as described in the chapters above.

 For a multichannel system please set the Profibus address of the second gateway as described on the gateway user manual. The default address of both modules is 5.

6.5 Example of procedural configuration with Profibus DP

Run **program 9** from Profibus DP interface and leave the system to stop it automatically when the program is at the end.

 Please pay attention to the settings of the stop/start parameter. The first value is 1 to start a program and 2 to leave the CDC90 to stop it automatically when the program is at the end. This function is integrated to avoid a restart of a program if the customer control system has a delay time.

Write the cyclic addresses as followed:

OPC UA Parameter name	Parameter descriptions	Profibus interface	Profibus address	Values
General_ProgramNr	Selected program identification number 1..10	Out	1	9

DCSOperatingMode	Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS/DCS control mode, 4 = Service mode 5 = Maintenance mode	Out	2	0
General_Start	Star/ Stop program: 1 = Start program 0 = Stop program 2 = CDC90 control stop program at the end	Out	3	1 after 2 when the program is running
General_Prg_Release_PRG_ERROR	Release error command 1= Repeat the last program step 2= Start the next program step 3= Abort program and stop all 4= Restart program	Out	4	
FieldOrDCSContrl	PLS/DCS Control 0 = Field device free control 1 = PLS/DCS control	Out	5	1
SelectChannelNr	Selected channel resp. meas. Point 1 = Channel 1 2 = Channel 2	Out	6	1 (for a second channel set this parameter to 2)

 A started program from PLS won't stop automatically. This should be stopped from the PLS as soon as the state parameter "Program end; input 19" is true. To let the system, stop the procedure automatically set the parameter "Program start/stop" to 2 when the procedure has started.

7 Modbus TCP Server

7.1 Functional principle

7.1.1 General

Modbus communication (unicast) uses a simple request-response mechanism.

There are three different scenarios:

If the device (server) receives a valid telegram with a valid request and can reply to it, it replies with a response telegram containing the function code of the request. If the device (server) receives an invalid telegram (e.g. CRC error), it does not reply. The application (client) must carry out an error diagnosis once a specified time (time-out) has elapsed. If the device (server) receives a valid telegram with an invalid request, it replies with a Modbus exception. The application (client) must carry out an error diagnosis.

As with RTU, the data is transmitted in binary format. Address and checksum used in RTU mode are dispensed with. The Modbus ADU is embedded in the TCP/IP telegram. Modbus TCP/IP ADU

MBAP header			Modbus PDU		
Transaction number	Protocol attribute	Number of bytes to follow	Address	Function	Data
2 Byte	2 Bytes	2 Bytes	1 Byte	1 Byte	N Bytes
= 0x0000		= N + 2	= 0		

Field	Length	Info	Client	Server
Transaction number	2 Byte	Identifies the transaction	Set by the client	Copied from the request into the reply
Protocol attribute	2 Byte		Set by the client	Copied from the request into the reply
Number of bytes to follow	2 Byte	Number of bytes to follow	Set by the client	Set by the server

Address	1 Byte	Identifies a slave that is connected to a serial bus located downstream. Note The devices in the Liquiline product family do not use the unit identifier. This should always be set to 0.	Set by the client	Copied from the request into the reply
---------	--------	---	-------------------	--

7.2 Liquiline Control CDC90 integration via Modbus TCP

The direct connection of CDC90 with customer control system PLS or DCS via Modbus TCP is possible. To write the parameters the PLS resp. DCS must send constantly the parameter (**Enable DCS/PLS control see table below**).

 Constantly writing this parameter means take control of the CDC90, no commands of the field device are accepted any more. Setting this parameter to zero does not give the PLS resp. DCS the possibility to write parameters or control the CDC90 anymore.

7.3 Command holding register data

The holding registers are used to configure and start programs of the CDC90.

Block	Setting	Remark
Type	Holding	
Function codes	03, 16	For Schneider PLS/DCS Write Data; %IW; %MW

 **Real** and **DWORD** parameters must be swapped on Siemens and Schneider control systems. We consider that a float value is built with the following format bytes AB CD, the swap function results in CD BA. Please note that these two systems are the ones validated from our system integration.

 Schneider control systems must use the WRITE_DATA function with the code %IW.

 Take control of Liquiline Control CDC90 from PLS resp. DCS means: Permanently set the parameter determining the control from PLS "**Enable DCS/PLS**" to 1 (see the following description). During that time, it is not possible to set or configure any parameter from the field device. If this parameter is set back to zero, the CDC90 will stop program running at its last step. The field device is then free to be configured.

7.3.1 Program control parameters

Write/Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register		Unit
					Channel 1	Channel 2	
Selected program number Range: 1-10	General_ProgramNr	BYTE	WORD	2	0	200	NONE
Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS DCS mode, 4 = Service mode, 5 = Assembly maintenance	DCSOperatingMode	BYTE	WORD	2	1	201	NONE
Program start/stop 1= Start selected program 0= Stop program 2= Stop automatically after starting (without closing the connection to PLS)	General_Start	BOOL	WORD	2	2	202	NONE
Command when a program error occurred 1= Restart last program step 2= Start next program step	General_Prg_Release_PR G_ERROR	BYTE	WORD	2	3	203	NONE

3= Stop / Abort program
4= Restart program

Enable DCS/PLS control	FieldOrDCSContrl	BOOL	WORD	2	4	204	NONE
Channel selection [1..2]	SelectChannelNr	USINT	WORD	2	5	205	NONE

7.3.2 Limit parameters

To set the limit parameters the PLS resp. DCS should set the operating mode on value 3 and the **“Enable DCS/PLS”** control parameter (PLS DCS mode see chapter above). The parameter combination is as follows:

Parameter	Value
Selected program number	
Operating mode	3
Program start/stop	
Command when a program error occurred	
Enable DCS/PLS control	1
Channel selection [1..2]	1

Write/Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register	Modbus TCP Register	Unit
					Channel 1	Channel	
Limit max. offset pH	MaxpHOffset	REAL	2xWORD	4	6	206	pH
Limit max. slope	MaxResultSlope	REAL	2xWORD	4	8	208	pH/mV
Limit min. slope	MinResultSlope	REAL	2xWORD	4	10	210	pH/mV
Limit delta slope	MaxResultDeltaSlope	REAL	2xWORD	4	12	212	pH/mV
Limit max. zero point	MaxResultZeroPt	REAL	2xWORD	4	14	214	pH
Limit min. zero point	MinResultZeroPt	REAL	2xWORD	4	16	216	pH
Limit delta zero point	MaxResultDeltaZeroPt	REAL	2xWORD	4	18	218	pH
Limit max. operation point	MaxResultOperationPt	REAL	2xWORD	4	20	220	pH
Limit min. operation point	MinResultOperationPt	REAL	2xWORD	4	22	222	pH
Limit delta operation point	MaxResultDeltaOperationPt	REAL	2xWORD	4	24	224	pH
Limit max. offset temperature	MaxTempOffset	REAL	2xWORD	4	26	226	Delta Kelvin
Control limit assembly	TranslationControlSwitch	BOOL	WORD	2	28	228	NONE
Limit number of assembly movements (Warning)	WarnLimitNumOfTranslation	UINT	WORD	2	29	229	NONE

Limit number of assembly movements (Alarm)	AlarmLimitNumOfTranslation	UINT	WORD	2	30	230	NONE
Control limit pump	LimitSwitchCtrl	BOOL	WORD	2	31	231	NONE
Limit max. volume pump (warning)	WarnLimVolPump1	REAL	2xWORD	4	32	232	Liter
Limit max. volume pump (alarm)	AlarmLimVolPump1	REAL	2xWORD	4	34	234	Liter
Limit operating time pump (warning)	WarnOptimePump	REAL	2xWORD	4	36	236	Days
Limit operating time pump (alarm)	AlarmOptimePump	REAL	2xWORD	4	38	238	Days
Control limit canisters	CanLimitSwitchCtrl	BOOL	WORD	2	40	240	NONE
Limit remaining volume canister 1	WarningRestVolumnCan1	REAL	2xWORD	4	41	241	Liter
Limit remaining volume canister 2	WarningRestVolumnCan2	REAL	2xWORD	4	43	243	Liter
Limit remaining volume canister 3	WarningRestVolumnCan3	REAL	2xWORD	4	45	245	Liter
Limit operating time canister 1	OperatingTlmeCan1	REAL	2xWORD	4	47	247	Days
Limit operating time canister 2	OperatingTlmeCan2	REAL	2xWORD	4	49	249	Days
Limit operating time canister 3	OperatingTlmeCan3	REAL	2xWORD	4	51	251	Days
Date time of the system	SetSystemTime	UDINT	DWORD	4	53	253	SINCE 01.01.1 970, 00:00; YYYY- MM-DD

							HH:MM :SS
Control limit of sensor	SensorLimitControlSwitch	BOOL	WORD	2	55	255	NONE
Limit operating time sensor (alarm)	SensorAlarmOpTime	REAL	2xWORD	4	56	256	Days
Limit operating time sensor (warning)	SensorWarningOpTime	REAL	2xWORD	4	58	258	Days
Limit number calibration (warning)	SensorWarningCalibNumber	REAL	2xWORD	4	60	260	Days
Limit number calibration (alarm)	SensorAlarmCalibNumber	REAL	2xWORD	4	62	262	NONE

7.4 Input register data

The data container of this block includes status, alarms, warnings, measurement values, calibration data and device information.

Block	Setting	Remark
Type	Input	
Function codes	04	For Schneider PLS/DCS Write Data; %MW

7.4.1 Media control unit alarm parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register		Unit
					Channel 1	Channel 2	
Canister 2 nearly empty	CanisterLevel2_1Warning	BOOL	WORD	2	0	200	NONE
Pump 2 active	Pump2On	BOOL	WORD	2	1	201	NONE
Canister 3 nearly empty	CanisterLevel3_1Warning	BOOL	WORD	2	2	202	NONE
Pump 3 active	Pump3On	BOOL	WORD	2	3	203	NONE
Canister 1 nearly empty	CanisterLevel1_1Warning	BYTE	WORD	2	4	204	NONE
Pump 1 active	Pump1On	BOOL	WORD	2	5	205	NONE
Air pressure measured	PressureSwitchAirIn	BOOL	WORD	2	6	206	NONE
Communication error between controller and pilot valve block	CommErrorPilotValveBuffer Provider	BOOL	WORD	2	7	207	NONE
Communication error between controller and remote IO	CommErrorRemotelIOBuffer Provider	BOOL	WORD	2	8	208	NONE
Canister 2 empty	FeedbackFillLevel2_1_Emp ty	BOOL	WORD	2	9	209	NONE

Canister 3 empty	FeedbackFillLevel3_1_Emp ty	BOOL	WORD	2	10	210	NONE
Canister 1 empty	FeedbackFillLevel1_1_Emp ty	BOOL	WORD	2	11	211	NONE

7.4.2 Program feedback parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register		Unit
					Channel 1	Channel 2	
Operating mode	OperatingMode	BYTE	WORD	2	12	212	NONE
Selected program	SelectedProgramm	BYTE	WORD	2	13	213	NONE
Time left till program step end	CurrentStepTime	INT	WORD	2	14	214	Seconds
Current program step number	Program1CurrentStep	INT	WORD	2	15	215	NONE
Program ready to run	Program1ReadyForStart	BOOL	WORD	2	16	216	NONE
Program abort	Program1Abort	BOOL	WORD	2	17	217	NONE
Program ended	Program1Ended	BOOL	WORD	2	18	218	NONE
Error code during the execution of the program	ErrorNumber	UINT	WORD	2	19	219	NONE

7.4.3 Assembly signals

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register		Unit
					Channel 1	Channel 2	
Assembly in service position	AssemblyServicepOosition	BOOL	WORD	2	20	220	NONE
Assembly in meas. Position	AssemblyMeaspOosition	BOOL	WORD	2	21	221	NONE
Provide air pressure	ProvidedPressure	BOOL	WORD	2	22	222	NONE

7.4.4 Transmitter measurement values

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register		Unit
					Channel 1	Channel 2	
Alarm transmitter CM42	CM42_ALM_CODE	INT	WORD	2	23	223	NONE
pH value	pHValue	REAL	2xWORD	4	24	224	pH
State pH value	pH_State	BYTE	WORD	2	26	226	NONE

mV value	mV_Value	REAL	2xWORD	4	27	227	mV
State mV value	mV_State	BYTE	WORD	2	29	229	NONE
Impedance value	GlassImp	REAL	2xWORD	4	30	230	Mega Ohm
State impedance value	GlassImp_State	BYTE	WORD	2	32	232	NONE
Temperature value	MeasTemperature	REAL	2xWORD	4	33	233	°C
State temperature value	Temperature_State	BYTE	WORD	2	35	235	NONE
Alarm critic transmitter	Transmitter_Sum_Alm	BOOL	WORD	2	36	236	NONE
Warning critic transmitter	Transmitter_Sum_Warn	BOOL	WORD	2	37	237	NONE
Alarm Impedance	Transmitter_GlasAlarm	BOOL	WORD	2	38	238	NONE
Alarm glass	Transmitter_Glasbruch	BOOL	WORD	2	39	239	NONE

7.4.5 Sensor calibration and sensor information

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte	Modbus TCP Register	Modbus TCP Register	Unit
Alarm zero point	ZeroPointOutOfRange	BOOL	WORD	2	40	240	NONE

Alarm slope	SlopeOutOfrange	BOOL	WORD	2	41	241	NONE
Alarm delta zero point	DeltaZeroPointOutOfRange	BOOL	WORD	2	42	242	NONE
Alarm delta slope	DeltaSlopeOutOfRange	BOOL	WORD	2	43	243	NONE
pH unstable during calibration	Transmitter_pH_Instabil	BOOL	WORD	2	44	244	NONE
Remote communication error	Transmitter_Remote_Cal_Abort	BOOL	WORD	2	45	245	NONE
Offset pH out of limit	pHOffsetOutOfRange	BOOL	WORD	2	46	246	
Operation point out of limit	OperationPointOutOfRange	BOOL	WORD	2	47	247	
Temperature offset out of limit	TempOffsetOutOfRange	BOOL	WORD	2	48	248	
Zero point	ZeroPoint	REAL	2xWORD	4	49	249	pH
Slope	Slope	REAL	2xWORD	4	51	251	pH/mV
Delta Zero point	DeltaZeroPoint	REAL	2xWORD	4	53	253	pH
Delta Slope	DeltaSlope	REAL	2xWORD	4	55	255	pH/mV
Max. meas. Temperature	MaxTemp	REAL	2xWORD	4	57	257	°C
operating time sensor	OpHours	REAL	2xWORD	4	59	259	Hours

operating time sensor > 80 °C	OpHours80	REAL	2xWORD	4	61	261	Hours
operating time sensor > 100 °C	OpHours100	REAL	2xWORD	4	63	263	Hours
operating time sensor > 300 mV	OpHours300mV	REAL	2xWORD	4	65	265	Hours
Operating time sensor < 300mV	OpHoursMin300mV	REAL	2xWORD	4	67	267	Hours
Number of sensor adjustment	NumCalibration	INT	WORD	2	69	269	NONE
Adjustment type	ADJ_CAL	BYTE	WORD	2	70	270	NONE
Adjustment date	Adjustement_Date	DATE	DWORD	4	71	271	SINCE 01.01.1970, 00:00; YYYY- MM-DD HH:MM:SS
Adjusted Zero point	Adjustement_ZeroPoint	REAL	2xWORD	4	73	273	pH
Adjusted Slope	Adjustement_Slope	REAL	2xWORD	4	75	275	pH/mV
pH Meas. Value in buffer 7	Adjustement_pH1	REAL	2xWORD	4	77	277	pH
mV Meas. Value in buffer 7	Adjustement_mV1	REAL	2xWORD	4	79	279	mV

Meas. temperature Value in buffer 7	Adjustement_Temperatur1	REAL	2xWORD	4	81	281	°C
SCS meas. Value 1	Adjustement_SCS1	REAL	2xWORD	4	83	283	Mega Ohm
Response time till stability 1	Adjustement_ResponseTime 1	INT	WORD	2	85	285	Seconds
mV value 1 after 30 s	Adjustement_mV_T30_1	REAL	2xWORD	4	86	286	Seconds
pH Meas. Value in buffer 4	Adjustement_pH2	REAL	2xWORD	4	88	288	pH
mV Meas. Value in buffer 4	Adjustement_mV2	REAL	2xWORD	4	90	290	mV
Meas. temperature Value in buffer 4	Adjustement_Temperatur2	REAL	2xWORD	4	92	292	°C
SCS meas. Value 2	Adjustement_SCS2	REAL	2xWORD	4	94	294	Mega Ohm
Response time till stability 2	Adjustement_ResponseTime 2	INT	WORD	2	96	296	Seconds
mV value 2 after 30 s	Adjustement_mV_T30_2	REAL	2xWORD	4	97	297	Seconds
Operating point	OperatingPoint	REAL	2xWORD	4	158	358	mV
Delta operating point	DeltaOperatingPoint	REAL	2xWORD	4	160	360	mV

Adjusted operating point	Adjustment_OperatingPoint	REAL	2xWORD	4	162	362	mV
Reference impedance 1	Adjustment_ReflImpedance 1	REAL	2xWORD	4	164	364	MOhm
Reference impedance 2	Adjustment_ReflImpedance 2	REAL	2xWORD	4	166	366	MOhm
pH Offset	pHOffsetValue	REAL	2xWORD	4	168	368	pH
Offset pH out of limit	pHOffsetOutOfRange	BOOL	WORD	2	170	370	NONE
Operation point out of limit	OperationPointOutOfRange	BOOL	WORD	2	171	371	NONE
Delta Operation point out of limit	DeltaOperationPointOutOfRange	BOOL	WORD	2	172	372	NONE
Temperature offset out of limit	TempOffsetOutOfRange	BOOL	WORD	2	173	373	NONE

7.4.6 Media control unit and program parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Modbus TCP Register	Modbus TCP Register	Unit
-----------------	-----------------------	-----------	--------------	---------------------	---------------------	------

Program step number	Program1CurrentStep	UINT	WORD	99	299	NONE
Operating time canister 1	OperatingTimeCan1	UINT	WORD	100	300	Days
Operating time canister 2	OperatingTimeCan2	UINT	WORD	101	301	Days
Operating time canister 3	OperatingTimeCan3	UINT	WORD	102	302	Days
Remaining volume canister 1	RestVolumCanister1	REAL	2xWORD	103	303	Liter
Remaining volume canister 2	RestVolumCanister2	REAL	2xWORD	105	305	Liter
Remaining volume canister 3	RestVolumCanister3	REAL	2xWORD	107	307	Liter
Changing time canister 1	Canister1changingDate	UDINT	DWORD	109	309	SINCE 01.01.1970, 00:00; YYYY- MM-DD HH:MM:SS
Changing time canister 2	Canister2changingDate	UDINT	DWORD	111	311	SINCE 01.01.1970, 00:00; YYYY- MM-DD HH:MM:SS
Changing time canister 3	Canister3changingDate	UDINT	DWORD	113	313	SINCE 01.01.1970, 00:00; YYYY- MM-DD HH:MM:SS

Number of movement of the assembly	NumberOfAssemblyTransl ation	UDINT	DWORD	115	315	NONE
Operating time pump 1	OpTimePump1	REAL	2xWORD	117	317	Days
Operating time pump 2	OpTimePump2	REAL	2xWORD	119	319	Days
Operating time pump 3	OpTimePump3	REAL	2xWORD	121	321	Days
System date time	SetSystemTime	UDINT	DWORD	123	323	SINCE 01.01.1970, 00:00; YYYY- MM-DD HH:MM:SS

7.5 Example of procedural configuration with Modbus TCP Master

Run **program 9** from Modbus TCP interface and leave the system to stop it automatically when the program is at the end.



Please pay attention to the settings of the stop/start parameter. The first value is 1 to start a program and 2 to leave the CDC90 to stop it automatically when the program is at the end. This function is integrated to avoid a restart of a program if the customer control system has a delay time.

Write the cyclic registers as followed:

OPC UA Parameter name	Parameter descriptions	Data to write:	Parameter values
-----------------------	------------------------	----------------	------------------

Code FC: 16

General_ProgramNr	Selected program identification number 1..10	0	9
DCSOperatingMode	Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS/DCS control mode, 4 = Service mode 5 = Maintenance mode	1	0
General_Start	Star/ Stop program: 1 = Start program 0 = Stop program 2 = CDC90 control stop program at the end	2	1 after 2 when the program started
General_Prg_Release_PRG_ERROR	Release error command 1= Repeat the last program step 2= Start the next program step 3= Abort program and stop all 4= Restart program	3	
FieldOrDCSContrl	PLS/DCS Control 0 = Field device free control	4	1

	1 = PLS/DCS control		
SelectChannelNr	Selected channel resp. meas. Point	5	1 (for a second channel set this parameter to 2)
	1 = Channel 1		
	2 = Channel 2		

8 Ethernet IP data connection

The direct connection of CDC90 with customer control system PLS or DCS via Ethernet IP is possible. To write the parameters, the PLS resp. DCS must send constantly the parameter (**Enable DCS/PLS control see table below**).

8.1 Network settings

The network settings can be made via local operation or via the Web server IP-address: 8080/cdc90.htm (the default page is 192.168.0.1: 8080/CDC90.htm).

8.2 Integration into a control system

8.2.1 EDS file

The electronic data sheet (EDS) file can be obtained from the following sources:

<https://www.endress.com/en/Field-instruments-overview/liquid-analysis-product-overview/pH-sensor-automatic-cleaning-calibration-cdc90>



Constantly writing this parameter means take control of the CDC90, no commands of the field device are accepted any more. Setting this parameter to zero does not give the PLS resp. DCS the possibility to write parameters or control the CDC90 anymore.

8.3 Input data



Take control of Liquiline Control CDC90 from PLS resp. DCS means: Permanently set the parameter determining the control from PLS "**Enable DCS/PLS**" to 1 (see the following description). During that time, it is not possible to set or configure any parameter from the field device. If this parameter is set back to zero, the CDC90 will stop the program running at the last step. The field device is then free to be configured.

8.3.1 Program control parameters

Write/Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Input data	Bytes	Bytes	Unit
						Channel 1	Channel 2	
Selected program number Range: 1-10	General_ProgramNr	USINT	BYTE	2	1	1	7	NONE
Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS DCS mode, 4 = Service mode, 5 = Assembly maintenance	DCSOperatingMode	USINT	BYTE	2	2	2	8	NONE
Program start/stop 1= Start selected program 0= Stop program 2= Stop automatically after starting (without closing the connection to PLS)	General_Start	BOOL	BYTE	2	3	3	9	NONE
Command when a program error occurred 1= Restart last program step 2= Start next program step	General_Prg_Release_PRG_ERROR	USINT	BYTE	2	4	4	10	NONE

3= Stop / Abort program
 4= Restart program

Enable DCS/PLS control	FieldOrDCSContrl	BOOL	BYTE	2	5	5	11	NONE
Channel selection [1..2]	SelectChannelNr	USINT	BYTE	2	6	6	12	NONE

8.4 Output data

The data container of this block includes status, alarms, warnings, measurement values, calibration data and device information.

8.4.1 Media control unit alarm parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes	Bytes	Unit
						Channel 1	Channel 2	
Pump canister and assembly states	PumpCanisterAssemblyState	WORD	WORD	2	1	1, 2	175, 176	NONE
CanisterLevel2_1Warning		BIT			1			
Pump2On		BIT			2			
CanisterLevel3_1Warning		BIT			3			

Pump3On	BIT 4
CanisterLevel1_1Warning	BIT 5
Pump1On	BIT 6
PressureSwitchAirIn	BIT 7
CommErrorPilotValveBufferProvider	BIT 8
CommErrorRemotelOBufferProvider	BIT 9
FeedbackFillLevel2_1_Empty	BIT 10
FeedbackFillLevel3_1_Empty	BIT 11
FeedbackFillLevel1_1_Empty	BIT 12
AssemblyServicePosition	BIT 13
AssemblyMeaspPosition	BIT 14
ProvidedPressure	BIT 15

8.4.2 Program feedback parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes	Unit
						Channel 1	Channel 2

Operating mode	OperatingMode	USINT	BYTE	2	2	3	177	NONE
Selected program	SelectedProgramm	USINT	BYTE	2	3	4	178	NONE
Time left till program step end	CurrentStepTime	INT	WORD	2	4	5, 6	179, 180	Seconds
Current program step number	Program1CurrentStep	INT	WORD	2	5	7, 8	181, 182	NONE
Program ready to run	Program1ReadyForStart	BOOL	BYTE	2	6	9	183	NONE
Program abort	Program1Abort	BOOL	BYTE	2	7	10	184	NONE
Program ended	Program1Ended	BOOL	BYTE	2	8	11	185	NONE
Error code during the execution of the program	ErrorNumber	UINT	WORD	2	9	12, 13	186, 187	NONE

8.4.3 Transmitter measurement values

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes	Bytes	Unit
						Channel 1	Channel 2	
Alarm transmitter CM42	CM42_ALM_CODE	INT	WORD	2	10	14, 15	188, 189	NONE
pH value	pHValue	REAL	2xWORD	4	11	16, 17, 18, 19	190, 191, 192, 193	pH

State pH value	pH_State	USINT	BYTE	2	12	20	194	NONE
mV value	mV_Value	REAL	2xWORD	4	13	21, 22, 23, 24	195, 196, 197, 198	mV
State mV value	mV_State	USINT	BYTE	2	14	25	199	NONE
Impedance value	GlassImp	REAL	2xWORD	4	15	26, 27, 28, 29	200, 201, 202, 203	Mega Ohm
State impedance value	GlassImp_State	USINT	BYTE	2	16	30	204	NONE
Temperature value	MeasTemperature	REAL	2xWORD	4	17	31, 32, 33, 34	205, 206, 207, 208	°C
State temperature value	Temperature_State	USINT	BYTE	2	18	35	209	NONE

8.4.4 Sensor calibration and sensor information

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes		Unit
						Channel 1	Channel 2	
Process parameter monitoring	ProcessParameter OutOfRange	WORD	WORD	2	19	36, 37	210, 211	NONE

Transmitter_Sum_Alm	BIT 1
Transmitter_Sum_Warn	BIT 2
Transmitter_GlasAlarm	BIT 3
Transmitter_Glasbruch	BIT 4
ZeroPointOutOfRange	BIT 5
SlopeOutOfrange	BIT 6
DeltaZeroPointOutOfRange	BIT 7
DeltaSlopeOutOfRange	BIT 8
Transmitter_pH_Instabil	BIT 9
Transmitter_Remote_Cal_Abort	BIT 10
pHOffsetOutOfRange	BIT 11
OperationPointOutOfRange	BIT 12
TempOffsetOutOfRange	BIT 13
pHOffsetOutOfRange	BIT 14
OperationPointOutOfRange	BIT 15
DeltaOperationPointOutOfRange	BIT 16

Zero point	ZeroPoint	REAL	2xWORD	4	20	38, 39,	212, 213,	pH
------------	-----------	------	--------	---	----	---------	-----------	----

						40, 41	214, 215	
Slope	Slope	REAL	2xWORD	4	21	42, 43,	216, 217,	pH/mV
						44, 45	218, 219	
Delta Zero point	DeltaZeroPoint	REAL	2xWORD	4	22	46, 47,	220, 221,	pH
						48, 49	222, 223	
Delta Slope	DeltaSlope	REAL	2xWORD	4	23	50, 51,	224, 225,	pH/mV
						52, 53	226, 227	
Max. meas. Temperature	MaxTemp	REAL	2xWORD	4	24	54, 55,	228, 229,	°C
						56, 57	230, 231	
operating time sensor	OpHours	REAL	2xWORD	4	25	58, 59,	232, 233,	Hours
						60, 61	234, 235	
Number of sensor adjustment	NumCalibration	INT	WORD	2	26	62, 63	236, 237	NONE
Adjustment type	ADJ_CAL	USINT	BYTE		27	64	238	NONE
Adjustment date	Adjustement_Date	DATE	2xWORD	8	28	65, 66,	239, 240,	SINCE
						67, 68	241, 242	01.01.1970,
								00:00;
								YYYY-MM-
								DD
								HH:MM:SS

Zero point	Adjustement_Zero Point	REAL	2xWORD	4	29	69, 70, 71, 72	243, 244, 245, 246	pH
Slope	Adjustement_Slope	REAL	2xWORD	4	30	73, 74, 75, 76	247, 248, 249, 250	pH/mV
pH Meas. Value in buffer 7	Adjustement_pH1	REAL	2xWORD	4	31	77, 78, 79, 80	251, 252, 253, 254	pH
mV Meas. Value in buffer 7	Adjustement_mV1	REAL	2xWORD	4	32	81, 82, 83, 84	255, 256, 257, 258	mV
Meas. temperature Value in buffer 7	Adjustement_Temperatur1	REAL	2xWORD	4	33	85, 86, 87, 88	259, 260, 261, 262	°C
SCS meas. Value 1	Adjustement_SCS1	REAL	2xWORD	4	34	89, 90, 91, 92	263, 264, 265, 266	Mega Ohm
Response time till stability 1	Adjustement_ResponseTime1	INT	WORD	2	35	93, 94	267, 268	Seconds
mV value 1 after 30 s	Adjustement_mV_T30_1	REAL	2xWORD	4	36	95, 96, 97, 98	269, 270, 271, 272	Seconds
pH Meas. Value in buffer 4	Adjustement_pH2	REAL	2xWORD	4	37	99, 100, 101, 102	273, 274, 275, 276	pH

mV Meas. Value in buffer 4	Adjustement_mV2	REAL	2xWORD	4	38	103, 104, 105, 106	277, 278, 279, 280	mV
Meas. temperature Value in buffer 4	Adjustement_Temperatur2	REAL	2xWORD	4	39	107, 108, 109, 110	281, 282, 283, 284	°C
SCS meas. Value 2	Adjustement_SCS2	REAL	2xWORD	4	40	111, 112, 113, 114	285, 286, 287, 288	Mega Ohm
Response time till stability 2	Adjustement_ResponseTime2	INT	WORD	2	41	115, 116	289, 290	Seconds
mV value 2 after 30 s	Adjustement_mV_T30_2	REAL	2xWORD	4	42	117, 118, 119, 120	291, 292, 293, 294	Seconds
Operating point	OperatingPoint	REAL	2xWORD	4	43	121, 122, 123, 124	295, 296, 297, 298	mV
Delta operating point	DeltaOperatingPoint	REAL	2xWORD	4	44	125, 126, 127, 128	299, 300, 301, 302	mV
Adjusted operating point	Adjustement_OperatingPoint	REAL	2xWORD	4	45	129, 130, 131, 132	303, 304, 305, 306	mV
pH Offset	pHOffsetValue	REAL	2xWORD	4	46	133, 134, 135, 136	307, 308, 309, 310	pH

8.4.5 Media control unit and program parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes		Unit
						Channel 1	Channel 2	
Operating time canister 1	OperatingTimeCan1	UINT	WORD	4	47	137, 138	311, 312	Days
Operating time canister 2	OperatingTimeCan2	UINT	WORD	4	48	139, 140	313, 314	Days
Operating time canister 3	OperatingTimeCan3	UINT	WORD	4	49	141, 142	315, 316	Days
Remaining volume canister 1	RestVolumCanister1	REAL	2xWORD	4	50	143, 144, 145, 146	317, 318, 319, 320	Liter
Remaining volume canister 2	RestVolumCanister2	REAL	2xWORD	4	51	147, 148, 149, 150	321, 322, 323, 324	Liter
Remaining volume canister 3	RestVolumCanister3	REAL	2xWORD	4	52	151, 152, 153, 154	325, 326, 327, 328	Liter
Number of movement of the assembly	NumberOfAssemblyTranslation	UDINT	DWORD	4	53	155, 156, 157, 158	329, 330, 331, 332	NONE
Operating time pump 1	OpTimePump1	REAL	2xWORD	4	54	159, 160,	333, 334,	Days

						161, 162	335, 336	
Operating time pump 2	OpTimePump2	REAL	2xWORD	4	55	163, 164,	337, 338,	Days
						165, 166	339, 340	
Operating time pump 3	OpTimePump3	REAL	2xWORD	4	56	167, 168,	341, 342,	Days
						169, 170	343, 344	
System date time	SetSystemTime	UDINT	DWORD	4	57	171, 172,	NOT	SINCE
						173, 174	DEFINED	01.01.
								1970,
								00:00;
								YYYY-
								MM-
								DD
								HH:MM
								:SS

8.5 Example of procedural configuration with Ethernet IP

Run **program 9** from Ethernet IP interface and leave the system to stop it automatically when the program is at the end.

 Please pay attention to the settings of the stop/start parameter. The first value is 1 to start a program and 2 to leave the CDC90 to stop it automatically when the program is at the end. This function is integrated to avoid a restart of a program if the customer control system has a delay time.

Write the cyclic registers as followed:

OPC UA Parameter name	Parameter descriptions	Input	Parameter values
General_ProgramNr	Selected program identification number 1..10	0	9
DCSOperatingMode	Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS/DCS control mode, 4 = Service mode 5 = Maintenance mode	1	0
General_Start	Star/ Stop program: 1 = Start program 0 = Stop program 2 = CDC90 control stop program at the end	2	1 after 2 when the program started
General_Prg_Release_PRG_ERROR	Release error command 1= Repeat the last program step 2= Start the next program step 3= Abort program and stop all 4= Restart program	3	
FieldOrDCSContrl	PLS/DCS Control 0 = Field device free control	4	1

	1 = PLS/DCS control		
SelectChannelNr	Selected channel resp. meas. Point	5	1
	1 = Channel 1		
	2 = Channel 2		

9 Profinet data connection

The direct connection of CDC90 with customer control system PLS or DCS via Profinet IO is possible. To write the parameters, the PLS resp. DCS must send constantly the parameter **(Enable DCS/PLS control see table below)**.

The data transfer to a PLS or DCS for a standard CDC90, is done via a gateway (Modbus TCP/ Profinet IO). **For special project, we use different controller which allows a direct connection without gateway.** To connect the customer control system to CDC90, the customer control system must be connected to the gateway first.




9. Pic. Gateway connection with CDC90 Ethernet switch

 Please read the installation manual of the gateway enclosed to the Liquiline Control CDC90.

9.1 Setting the device address

The default Modbus TCP address is 192.168.0.7. To change the device address, please read the manual of the gateway and set the IP address node on CDC90 corresponding to your new gateway IP address. To set the IP address node navigate to: Menu/Setup/System settings/Communication/Transmitter connection/Gateway




10. Pic. Setting visualization Profinet IO IP address



11. Pic. None DHCP IP address configuration (CH1: 192.168.0.5 and CH1: 192.168.0.6)

9.2 Configuration of the process data for PROFINET IO

Upload the GSDML file “GSDML-V2.3-HMS-ANYBUS_X_GATEWAY_PROFINET_IO-20151023” to the PLS resp. DCS system. Insert data output module (8 bytes and 16 bytes) and data input module (256 bytes, 64 bytes, 32 and 4 bytes).



12. Pic. Representation of the data container of the gateway on Wago (Codesys)

9.3 Integration into a control system

9.3.1 GSDML file

The electronic data sheet (GSDML) file can be obtained from the following sources:

<https://www.endress.com/en/Field-instruments-overview/liquid-analysis-product-overview/pH-sensor-automatic-cleaning-calibration-cdc90>

SD01518C/07/EN/01.17

 Constantly writing this parameter means take control of the CDC90, no commands of the field device are accepted any more. Setting this parameter to zero does not give the PLS resp. DCS the possibility to write parameters or control the CDC90 anymore.

9.4 Input data

 Take control of Liquiline Control CDC90 from PLS resp. DCS means: Permanently set the parameter determining the control from PLS "**Enable DCS/PLS**" to 1 (see the following description). During that time, it is not possible to set or configure any parameter from the field device. If this parameter is set back to zero, the CDC90 will stop the program running at the last step. The field device is then free to be configured.

9.4.1 Program control parameters

Write/Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Input data	Bytes	Bytes	Unit
						Channel 1	Channel 2	
Selected program number Range: 1-10	General_ProgramNr	USINT	WORD	2	1	1, 2	13, 14	NONE
Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS DCS mode, 4 = Service mode, 5 = Assembly maintenance	DCSOperatingMode	USINT	WORD	2	2	3, 4	15, 16	NONE
Program start/stop 1= Start selected program 0= Stop program 2= Stop automatically after starting (without closing the connection to PLS)	General_Start	BOOL	WORD	2	3	5, 6	17, 18	NONE
Command when a program error occurred 1= Restart last program step 2= Start next program step	General_Prg_Release_PRG_ERROR	USINT	WORD	2	4	7, 8	19, 20	NONE

3= Stop / Abort program
 4= Restart program

Enable DCS/PLS control	FieldOrDCSContrl	BOOL	WORD	2	5	9, 10	21, 22	NONE
Channel selection [1..2]	SelectChannelNr	USINT	WORD	2	6	11, 12	23, 24	NONE

9.5 Output data

The data container of this block includes status, alarms, warnings, measurement values, calibration data and device information.

9.5.1 Media control unit alarm parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes	Bytes	Unit
						Channel 1	Channel 2	
Pump canister and assembly states	PumpCanisterAsse mblyState	WORD	WORD	2	1	1, 2	181, 182	NONE
CanisterLevel2_1Warning		BIT		1				

Pump2On	BIT 2
CanisterLevel3_1Warning	BIT 3
Pump3On	BIT 4
CanisterLevel1_1Warning	BIT 5
Pump1On	BIT 6
PressureSwitchAirIn	BIT 7
CommErrorPilotValveBufferProvider	BIT 8
CommErrorRemotelIOBufferProvider	BIT 9
FeedbackFillLevel2_1_Empty	BIT 10
FeedbackFillLevel3_1_Empty	BIT 11
FeedbackFillLevel1_1_Empty	BIT 12
AssemblyServicePosition	BIT 13
AssemblyMeasPosition	BIT 14
ProvidedPressure	BIT 15

9.5.2 Program feedback parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes		Unit
						Channel 1	Channel 2	
Operating mode	OperatingMode	USINT	WORD	2	2	3, 4	183, 184	NONE
Selected program	SelectedProgramm	USINT	WORD	2	3	5, 6	185, 186	NONE
Time left till program step end	CurrentStepTime	INT	WORD	2	4	7, 8	187, 188	Seconds
Current program step number	Program1CurrentStep	INT	WORD	2	5	9, 10	189, 190	NONE
Program ready to run	Program1ReadyForStart	BOOL	WORD	2	6	11, 12	191, 192	NONE
Program abort	Program1Abort	BOOL	WORD	2	7	13, 14	193, 194	NONE
Program ended	Program1Ended	BOOL	WORD	2	8	15, 16	195, 196	NONE
Error code during the execution of the program	ErrorNumber	UINT	WORD	2	9	17, 18	197, 198	NONE

9.5.3 Transmitter measurement values

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes		Unit
						Channel 1	Channel 2	
Alarm transmitter CM42	CM42_ALM_CODE	INT	WORD	2	10	19, 20	199, 200	NONE

pH value	pHValue	REAL	2xWORD	4	11	21, 22, 23, 24	201, 202, 203, 204	pH
State pH value	pH_State	USINT	WORD	2	12	25, 26	205, 206	NONE
mV value	mV_Value	REAL	2xWORD	4	13	27, 28, 29, 30	207, 208, 209, 210	mV
State mV value	mV_State	USINT	WORD	2	14	31, 32	211, 212	NONE
Impedance value	GlassImp	REAL	2xWORD	4	15	33, 34, 35, 36	213, 214, 215, 216	Mega Ohm
State impedance value	GlassImp_State	USINT	WORD	2	16	37, 38	217, 218	NONE
Temperature value	MeasTemperature	REAL	2xWORD	4	17	39, 40, 41, 42	219, 220, 221, 222	°C
State temperature value	Temperature_State	USINT	WORD	2	18	43, 44	223, 224	NONE

9.5.4 Sensor calibration and sensor information

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes		Unit
						Channel 1	Channel 2	

Process parameter monitoring		ProcessParameter OutOfRange	WORD	WORD	2	19	45, 46	225, 226	NONE
Transmitter_Sum_Alm	BIT 1								
Transmitter_Sum_Warn	BIT 2								
Transmitter_GlasAlarm	BIT 3								
Transmitter_Glasbruch	BIT 4								
ZeroPointOutOfRange	BIT 5								
SlopeOutOfrange	BIT 6								
DeltaZeroPointOutOfRange	BIT 7								
DeltaSlopeOutOfRange	BIT 8								
Transmitter_pH_Instabil	BIT 9								
Transmitter_Remote_Cal_Abort	BIT 10								
pHOffsetOutOfRange	BIT 11								
OperationPointOutOfRange	BIT 12								
TempOffsetOutOfRange	BIT 13								
pHOffsetOutOfRange	BIT 14								
OperationPointOutOfRange	BIT 15								

DeltaOperationPointOutOfRange BIT
 16

Zero point	ZeroPoint	REAL	2xWORD	4	20	47, 48, 49, 50	227, 228, 229, 230	pH
Slope	Slope	REAL	2xWORD	4	21	51, 52, 53, 54	231, 232, 233, 234	pH/mV
Delta Zero point	DeltaZeroPoint	REAL	2xWORD	4	22	55, 56, 57, 58	235, 236, 237, 238	pH
Delta Slope	DeltaSlope	REAL	2xWORD	4	23	59, 60, 61, 62	239, 240, 241, 242	pH/mV
Max. meas. Temperature	MaxTemp	REAL	2xWORD	4	24	63, 64, 65, 66	243, 244, 245, 246	°C
operating time sensor	OpHours	REAL	2xWORD	4	25	67, 68, 69, 70	247, 248, 249, 250	Hours
Number of sensor adjustment	NumCalibration	INT	WORD	2	26	71, 72	251, 252	NONE
Adjustment type	ADJ_CAL	USINT	WORD		27	73, 74	253, 254	NONE
Adjustment date	Adjustment_Date	DATE	2xWORD	8	28	75, 76, 77, 78	255, 256, 257, 258	SINCE 01.01.1970, 00:00;

								YYYY-MM-DD HH:MM:SS
Zero point	Adjustement_Zero Point	REAL	2xWORD	4	29	79, 80, 81, 82	259, 260, 261, 262	pH
Slope	Adjustement_Slop e	REAL	2xWORD	4	30	83, 84, 85, 86	263, 264, 265, 266	pH/mV
pH Meas. Value in buffer 7	Adjustement_pH1	REAL	2xWORD	4	31	87, 88, 89, 90	267, 268, 269, 270	pH
mV Meas. Value in buffer 7	Adjustement_mV1	REAL	2xWORD	4	32	91, 92, 93, 94	271, 272, 273, 274	mV
Meas. temperature Value in buffer 7	Adjustement_Tem peratur1	REAL	2xWORD	4	33	95, 96, 97, 98	275, 276, 277, 278	°C
SCS meas. Value 1	Adjustement_SCS 1	REAL	2xWORD	4	34	99, 100, 101, 102	279, 280, 281, 282	Mega Ohm
Response time till stability 1	Adjustement_Res ponseTime1	INT	WORD	2	35	103, 104	283, 284	Seconds
mV value 1 after 30 s	Adjustement_mV_ T30_1	REAL	2xWORD	4	36	105, 106,	285, 286,	Seconds

						107, 108	287, 288	
pH Meas. Value in buffer 4	Adjustement_pH2	REAL	2xWORD	4	37	109, 110,	289, 290,	pH
						111, 112	291, 292	
mV Meas. Value in buffer 4	Adjustement_mV2	REAL	2xWORD	4	38	113, 114,	293, 294,	mV
						115, 116	295, 296	
Meas. temperature Value in buffer 4	Adjustement_Temperatur2	REAL	2xWORD	4	39	117, 118,	297, 298,	°C
						119, 120	299, 300	
SCS meas. Value 2	Adjustement_SCS2	REAL	2xWORD	4	40	121, 122,	301, 302,	Mega Ohm
						123, 124	303, 304	
Response time till stability 2	Adjustement_ResponseTime2	INT	WORD	2	41	125, 126	305, 306	Seconds
mV value 2 after 30 s	Adjustement_mV_T30_2	REAL	2xWORD	4	42	127, 128,	307, 308,	Seconds
						129, 130	309, 310	
Operating point	OperatingPoint	REAL	2xWORD	4	43	131, 132,	311, 312,	mV
						133, 134	313, 314	
Delta operating point	DeltaOperatingPoint	REAL	2xWORD	4	44	135, 136,	315, 316,	mV
						137, 138	317, 318	

pH Offset	pHOffsetValue	REAL	2xWORD	4	46	139, 140, 141, 142	319, 320, 321, 322	pH
-----------	---------------	------	--------	---	----	-----------------------	-----------------------	----

9.5.5 Media control unit and program parameters

Read Parameters	OPC UA Parameter name	Data type	Digital Data	Byte size	Output	Bytes		Unit
						Channel 1	Channel 2	
Operating time canister 1	OperatingTimeCan1	UINT	WORD	4	47	143, 144	323, 324	Days
Operating time canister 2	OperatingTimeCan2	UINT	WORD	4	48	145, 146	325, 326	Days
Operating time canister 3	OperatingTimeCan3	UINT	WORD	4	49	147, 148	327, 328,	Days
Remaining volume canister 1	RestVolumCanister1	REAL	2xWORD	4	50	149, 150,	329, 330,	Liter
						151, 152	331, 332	
Remaining volume canister 2	RestVolumCanister2	REAL	2xWORD	4	51	153, 154,	333, 334,	Liter
						155, 156	335, 336	
Remaining volume canister 3	RestVolumCanister3	REAL	2xWORD	4	52	157, 158,	337, 338,	Liter
						159, 160	339, 340	

Number of movement of the assembly	NumberOfAssemblyTran slation	UDINT	DWORD	4	53	161, 162, 163, 164	341, 342, 343, 344	NONE
Operating time pump 1	OpTimePump1	REAL	2xWORD	4	54	165, 166, 167, 168	345, 346, 347, 348	Days
Operating time pump 2	OpTimePump2	REAL	2xWORD	4	55	169, 170, 171, 172	349, 350, 351, 352	Days
Operating time pump 3	OpTimePump3	REAL	2xWORD	4	56	173, 174, 175, 176	353, 354, 355, 356	Days
System date time	SetSystemTime	UDINT	DWORD	4	57	177, 178, 179, 180	NOT DEFINED	SINCE 01.01. 1970, 00:00; YYYY- MM- DD HH:MM :SS

9.6 Example of procedural configuration with Profinet IO

Run **program 9** from Profinet IO interface and leave the system to stop it automatically when the program is at the end.

 Please pay attention to the settings of the stop/start parameter. The first value is 1 to start a program and 2 to leave the CDC90 to stop it automatically when the program is at the end. This function is integrated to avoid a restart of a program if the customer control system has a delay time.

Write the cyclic registers as followed:

OPC UA Parameter name	Parameter descriptions	Input	Parameter values
General_ProgramNr	Selected program identification number 1..10	0	9
DCSOperatingMode	Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS/DCS control mode, 4 = Service mode 5 = Maintenance mode	1	0
General_Start	Star/ Stop program: 1 = Start program 0 = Stop program 2 = CDC90 control stop program at the end	2	1 after 2 when the program started

General_Prg_Release_PRG_ERROR	Release error command	3	
	1= Repeat the last program step		
	2= Start the next program step		
	3= Abort program and stop all		
	4= Restart program		
FieldOrDCSContrl	PLS/DCS Control	4	1
	0 = Field device free control		
	1 = PLS/DCS control		
SelectChannelNr	Selected channel resp. meas. Point	5	1
	1 = Channel 1		
	2 = Channel 2		

10 OPC UA Connection and data

The standard IP address of the CDC90 controller is 192.168.0.1. The OPC UA connection is done by choosing the server "OPC.tcp://192.168.0.1:4840 / CODESYS OPC-UA-Server". The data structure transfer is defined as followed:

10.1 Read/Write data

10.1.1 Program control parameters

Write/Read Parameters	OPC UA Parameter name	Data type	Unit
Selected program number Range: 1-10	General_ProgramNr	BYTE	NONE
Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS DCS mode, 4 = Service mode, 5 = Assembly maintenance	DCSOperatingMode	BYTE	NONE
Program start/stop 1= Start selected program 0= Stop program 2= Stop automatically after starting (without closing the connection to PLS)	General_Start	BOOL	NONE
Command when a program error occurred 1= Restart last program step 2= Start next program step 3= Stop / Abort program 4= Restart program	General_Prg_Release_PRG _ERROR	BYTE	NONE
Enable DCS/PLS control	FieldOrDCSContrl	BOOL	NONE
Channel selection [1..2]	SelectChannelNr	USINT	NONE

10.1.2 Limit parameters

To set the limit parameters the PLS resp. DCS has to set the operating mode on value 3 and the **“Enable DCS/PLS”** control parameter (PLS DCS mode see chapter above). The parameter combination is as follows:

Parameter	Value
Selected program number	
Operating mode	3
Program start/stop	
Command when a program error occurred	
Enable DCS/PLS control	1
Channel selection [1..2]	1

Write/Read Parameters	OPC UA Parameter name	Data type	Unit
Limit max. offset pH	MaxpHOffset	REAL	pH
Limit max. slope	MaxResultSlope	REAL	pH/mV
Limit min. slope	MinResultSlope	REAL	pH/mV
Limit delta slope	MaxResultDeltaSlope	REAL	pH/mV
Limit max. zero point	MaxResultZeroPt	REAL	pH
Limit min. zero point	MinResultZeroPt	REAL	pH
Limit delta zero point	MaxResultDeltaZeroPt	REAL	pH
Limit max. operation point	MaxResultOperationPt	REAL	pH
Limit min. operation point	MinResultOperationPt	REAL	pH

Limit delta operation point	MaxResultDeltaOperationP t	REAL	pH
Limit max. offset temperature	MaxTempOffset	REAL	Delta Kelvin
Control limit assembly	TranslationControlSwitch	BOOL	NONE
Limit number of assembly movements (Warning)	WarnLimitNumOfTranslatio n	UINT	NONE
Limit number of assembly movements (Alarm)	AlarmLimitNumOfTranslati on	UINT	NONE
Control limit pump	LimitSwitchCtrl	BOOL	NONE
Limit max. volume pump (warning)	WarnLimVolPump1	REAL	Liter
Limit max. volume pump (alarm)	AlarmLimVolPump1	REAL	Liter
Limit operating time pump (warning)	WarnOptimePump	REAL	Days
Limit operating time pump (alarm)	AlarmOptimePump	REAL	Days
Control limit canisters	CanLimitSwitchCtrl	BOOL	NONE
Limit remaining volume canister 1	WarningRestVolumnCan1	REAL	Liter
Limit remaining volume canister 2	WarningRestVolumnCan2	REAL	Liter
Limit remaining volume canister 3	WarningRestVolumnCan3	REAL	Liter
Limit operating time canister 1	OperatingTlmeCan1	REAL	Days
Limit operating time canister 2	OperatingTlmeCan2	REAL	Days
Limit operating time canister 3	OperatingTlmeCan3	REAL	Days
Date time of the system	SetSystemTime	UDINT	SINCE 01.01.1970 , 00:00; YYYY-MM- DD HH:MM:SS
Control limit of sensor	SensorLimitControlSwitch	BOOL	NONE
Limit operating time sensor (alarm)	SensorAlarmOpTime	REAL	Days

Limit operating time sensor (warning)	SensorWarningOpTime	REAL	Days
Limit number calibration (warning)	SensorWarningCalibNumber	REAL	Days
Limit number calibration (alarm)	SensorAlarmCalibNumber	REAL	NONE

10.2 Read only data

The data container of this block includes status, alarms, warnings, measurement values, calibration data and device information.

10.2.1 Media control unit alarm parameters

Read Parameters	OPC UA Parameter name	Data type	Unit
Canister 2 nearly empty	CanisterLevel2_1Warning	BOOL	NONE
Pump 2 active	Pump2On	BOOL	NONE
Canister 3 nearly empty	CanisterLevel3_1Warning	BOOL	NONE
Pump 3 active	Pump3On	BOOL	NONE
Canister 1 nearly empty	CanisterLevel1_1Warning	BYTE	NONE
Pump 1 active	Pump1On	BOOL	NONE
Air pressure measured	PressureSwitchAirIn	BOOL	NONE
Communication error between controller and pilot valve block	CommErrorPilotValveBuffer Provider	BOOL	NONE
Communication error between controller and remote IO	CommErrorRemoteIOBuffer Provider	BOOL	NONE
Canister 2 empty	FeedbackFillLevel2_1_Emp ty	BOOL	NONE
Canister 3 empty	FeedbackFillLevel3_1_Emp ty	BOOL	NONE

Canister 1 empty	FeedbackFillLevel1_1_Emp ty	BOOL	NONE
------------------	--------------------------------	------	------

10.2.2 Program feedback parameters

Read Parameters	OPC UA Parameter name	Data type	Unit
Operating mode	OperatingMode	BYTE	NONE
Selected program	SelectedProgramm	BYTE	NONE
Time left till program step end	CurrentStepTime	INT	Seconds
Current program step number	Program1CurrentStep	INT	NONE
Program ready to run	Program1ReadyForStart	BOOL	NONE
Program abort	Program1Abort	BOOL	NONE
Program ended	Program1Ended	BOOL	NONE
Error code during the execution of the program	ErrorNumber	UINT	NONE

10.2.3 Assembly signals

Read Parameters	OPC UA Parameter name	Data type	Unit
Assembly in service position	AssemblyServicepOosition	BOOL	NONE
Assembly in meas. Position	AssemblyMeaspOosition	BOOL	NONE
Provide air pressure	ProvidedPressure	BOOL	NONE

10.2.4 Transmitter measurement values

Read Parameters	OPC UA Parameter name	Data type	Unit
-----------------	-----------------------	-----------	------

Alarm transmitter CM42	CM42_ALM_CODE	INT	NONE
pH value	pHValue	REAL	pH
State pH value	pH_State	BYTE	NONE
mV value	mV_Value	REAL	mV
State mV value	mV_State	BYTE	NONE
Impedance value	GlassImp	REAL	Mega Ohm
State impedance value	GlassImp_State	BYTE	NONE
Temperature value	MeasTemperature	REAL	°C
State temperature value	Temperature_State	BYTE	NONE
Alarm critic Liquiline	Transmitter_Sum_Alm	BOOL	NONE
Alarm transmitter CM44	Transmitter_Sum_Warn	BOOL	NONE
Alarm Impedance	Transmitter_GlasAlarm	BOOL	NONE
Alarm glass	Transmitter_Glasbruch	BOOL	NONE
Alarm zero point	ZeroPointOutOfRange	BOOL	NONE
Alarm slope	SlopeOutOfrange	BOOL	NONE
Alarm delta zero point	DeltaZeroPointOutOfRange	BOOL	NONE
Alarm delta slope	DeltaSlopeOutOfRange	BOOL	NONE

10.2.5 Sensor calibration and sensor information

Read Parameters	OPC UA Parameter name	Data type	Unit
-----------------	-----------------------	-----------	------

pH unstable during calibration	Transmitter_pH_Instabil	BOOL	NONE
Remote communication error	Transmitter_Remote_Cal_Abort	BOOL	NONE
Offset pH out of limit	pHOffsetOutOfRange	BOOL	
Operation point out of limit	OperationPointOutOfRange	BOOL	
Temperature offset out of limit	TempOffsetOutOfRange	BOOL	
Zero point	ZeroPoint	REAL	pH
Slope	Slope	REAL	pH/mV
Delta Zero point	DeltaZeroPoint	REAL	pH
Delta Slope	DeltaSlope	REAL	pH/mV
Max. meas. Temperature	MaxTemp	REAL	°C
operating time sensor	OpHours	REAL	Hours
operating time sensor > 80 °C	OpHours80	REAL	Hours
operating time sensor > 100 °C	OpHours100	REAL	Hours
operating time sensor > 300 mV	OpHours300mV	REAL	Hours
Operating time sensor < 300mV	OpHoursMin300mV	REAL	Hours
Number of sensor adjustment	NumCalibration	INT	NONE
Adjustment type	ADJ_CAL	BYTE	NONE
Adjustment date	Adjustement_Date	DATE	SINCE 01.01.1970 , 00:00; YYYY-MM-DD HH:MM:SS
Zero point	Adjustement_ZeroPoint	REAL	pH
Slope	Adjustement_Slope	REAL	pH/mV
pH Meas. Value in buffer 4	Adjustement_pH1	REAL	pH

mV Meas. Value in buffer 4	Adjustement_mV1	REAL	mV
Meas. temperature Value in buffer 4	Adjustement_Temperatur1	REAL	°C
SCS meas. Value	Adjustement_SCS1	REAL	Mega Ohm
Response time till stability	Adjustement_ResponseTime1	INT	Seconds
mV value after 30 s	Adjustement_mV_T30_1	REAL	Seconds
pH Meas. Value in buffer 7	Adjustement_pH2	REAL	pH
mV Meas. Value in buffer 7	Adjustement_mV2	REAL	mV
Meas. temperature Value in buffer 7	Adjustement_Temperatur2	REAL	°C
SCS meas. Value	Adjustement_SCS2	REAL	Mega Ohm
Response time till stability	Adjustement_ResponseTime2	INT	Seconds
mV value after 30 s	Adjustement_mV_T30_2	REAL	Seconds

10.2.6 Media control unit and program parameters

Read Parameters	OPC UA Parameter name	Data type	Unit
Program step number	Program1CurrentStep	UINT	NONE
Operating time canister 1	OperatingTimeCan1	UINT	Days
Operating time canister 2	OperatingTimeCan2	UINT	Days
Operating time canister 3	OperatingTimeCan3	UINT	Days
Remaining volume canister 1	RestVolumCanister1	REAL	Liter

Remaining volume canister 2	RestVolumCanister2	REAL	Liter
Remaining volume canister 3	RestVolumCanister3	REAL	Liter
Changing time canister 1	Canister1changingDate	UDINT	SINCE 01.01.1970, 00:00; YYYY-MM-DD HH:MM:SS
Changing time canister 2	Canister2changingDate	UDINT	SINCE 01.01.1970, 00:00; YYYY-MM-DD HH:MM:SS
Changing time canister 3	Canister3changingDate	UDINT	SINCE 01.01.1970, 00:00; YYYY-MM-DD HH:MM:SS
Number of movement of the assembly	NumberOfAssemblyTran slation	UDINT	NONE
Operating time pump 1	OpTimePump1	UINT	Days
Operating time pump 2	OpTimePump2	UINT	Days
Operating time pump 3	OpTimePump3	UINT	Days
System date time	SetSystemTime	UDINT	SINCE 01.01.1970, 00:00; YYYY-MM-DD HH:MM:SS

10.2.7 Data mapping of the second channel resp. second measurement point

The list of data above is an array of data [1..8]. The data of the first measurement point is the data with the array index 1 and the data of the second measurement point has the array index 2.

10.3 Example of procedural configuration with OPC UA

Run **program 9** from Modbus TCP interface and leave the system to stop it automatically when the program is at the end.




Please pay attention to the settings of the stop/start parameter. The first value is 1 to start a program and 2 to leave the CDC90 to stop it automatically when the program is at the end. This function is integrated to avoid a restart of a program if the customer control system has a delay time.


Write the cyclic registers as followed:

OPC UA Parameter name	Parameter descriptions	Parameter values
General_ProgramNr	Selected program identification number 1..10	9
DCSOperatingMode	Operating mode 0 = Manual mode, 1 = Automatic mode, 2 = Stop, 3 = PLS/DCS control mode, 4 = Service mode 5 = Maintenance mode	0
General_Start	Star/ Stop program: 1 = Start program 0 = Stop program 2 = CDC90 control stop program at the end	1 after 2 when the program started
General_Prg_Release_PRG_ERROR	Release error command 1= Repeat the last program step 2= Start the next program step 3= Abort program and stop all 4= Restart program	
FieldOrDCSContrl	PLS/DCS Control 0 = Field device free control	1

	1 = PLS/DCS control
SelectChannelNr	Selected channel resp. meas. Point 1
	1 = Channel 1
	2 = Channel 2

Example with automation UaExpress:





The screenshot displays the UAExpert interface with the following components:

- Project Tree:** Shows a project structure with servers, objects, and resources. The selected object is `m_OpC-UA_Data[1]`.
- Data Access View:** A table showing data points with columns for ID, Server, Node ID, Display Name, Value, Datatype, Source Timestamp, and Server Time.

ID	Server	Node ID	Display Name	Value	Datatype	Source Timestamp	Server Time
1	CODESYS OPC...	N545String@ad...	UserIntr	0	Byte	12:08:54.490	12:08:54.49
2	CODESYS OPC...	N545String@ad...	UserIntr	0	Byte	12:08:54.490	12:08:54.49
3	CODESYS OPC...	N545String@ad...	UserIntr	0	Byte	12:08:54.490	12:08:54.49
4	CODESYS OPC...	N545String@ad...	pIar	3.40883	Float	12:08:08.407	12:10:08.40
- Attributes:** A list of object attributes such as `SourceProcessCode`, `ServerTimestamp`, `StatusCode`, `Datatype`, `NamespaceIndex`, `IdentifierType`, `Identifier`, `ValueRank`, `ArrayDimensions`, `AccessLevel`, `UserAccessLevel`, `MinimumSamplingInterval`, and `Historizing`.
- Log:** A list of system messages with columns for Timestamp, Source, Server, and Message.

Timestamp	Source	Server	Message
27.02.2017 11:10.	Reference Plugin	CODESYS OPC-UA_Server - None - No...	BrowseNext succeeded.
27.02.2017 11:10.	Reference Plugin	CODESYS OPC-UA_Server - None - No...	BrowseNext succeeded.
27.02.2017 11:10.	Reference Plugin	CODESYS OPC-UA_Server - None - No...	Browse succeeded.
27.02.2017 11:10.	Attribute Plugin	CODESYS OPC-UA_Server - None - No...	Read attributes of node 'N545String@ad...MpiC.X86.Application.CD_CC90_m_OpC-UA_Data[1]' succeeded [ret = Good].
27.02.2017 11:04.	DA Plugin	CODESYS OPC-UA_Server - None - No...	Item [N545String@ad...MpiC.X86.Application.CD_CC90_m_OpC-UA_Data[1].pIValue.VAr] succeeded - RevisedSamplingInterval=300, RevisedQueueSize=1, MonitoredItemId=4 [ret = Good].
27.02.2017 11:04.	DA Plugin	CODESYS OPC-UA_Server - None - No...	Item [N545String@ad...MpiC.X86.Application.CD_CC90_m_OpC-UA_Data[1].pIValue.VAr] succeeded - RevisedSamplingInterval=250, QueueSize=1, DiscardOldItems=1, ClientHandles=15
27.02.2017 11:04.	DA Plugin	CODESYS OPC-UA_Server - None - No...	Found existing subscription for ServerId: 3
27.02.2017 11:04.	AddressSpaceModel	CODESYS OPC-UA_Server - None - No...	QmcDataModel-dropMimeData
27.02.2017 11:04.	TypeCache	CODESYS OPC-UA_Server - None - No...	Display Name = Float
27.02.2017 11:04.	TypeCache	CODESYS OPC-UA_Server - None - No...	Display Name = B.Float
27.02.2017 11:04.	TypeCache	CODESYS OPC-UA_Server - None - No...	Read succeeded.
27.02.2017 11:04.	TypeCache	CODESYS OPC-UA_Server - None - No...	Reading type info of NodeId NS00.NumericID
27.02.2017 11:04.	TypeCache	CODESYS OPC-UA_Server - None - No...	ValueRank = 1

11 Default possible program

11.1 Cleaning and flush programs

11.1.1 Cleaning and flush program with sensor staying in service position

Cleaning program: Sensor stays in service position

Steps	Time till next step	Remark
Service position	5	
Water	60	
Air	5	
Cleaner	4	Must be adapted to installation
Wait	120	
Water	60	
End	3	The sensor stays in service position

Cleaning program with back pressure: Sensor stays in service.

Position

Steps	Time till next step	Remark
Water	5	
H2O + Service Pos.	60	
Air	5	

Cleaner	4	Must be adapted to installation
Wait	120	
Water	60	
End	3	The sensor stays in service position

Flush program: Sensor stays in service position

Steps	Time till next step	Remark
Service position	5	
Water	40	
Wait	2	
Water	60	Must be adapted to application properties
Air	5	
Water	10	
End	3	The sensor stays in service position

Flush program with back pressure: Sensor stays in service position

Steps	Time till next step	Remark
Service position	5	


Water	40	
Wait	2	
Water	60	Must be adapted to application properties
Air	5	
Water	10	
End	3	The sensor stays in service position

11.1.2 Cleaning and flush program with sensor back to measurement position

Cleaning program: Sensor back in meas. position

Steps	Time till next step	Remark
Service position	5	
Water	60	
Air	5	
Cleaner	4	Must be adapted to installation
Wait	120	
Water	30	
Wait	3	
Measure position	5	

End 3 The sensor back goes
back to meas. position



**Cleaning program with back pressure: Sensor back to meas.
position**

Steps	Time till next step	Remark
Water	5	
H2O + Service Pos.	60	
Air	5	
Cleaner	4	Must be adapted to installation
Wait	120	
Water	60	
H2O + Meas. Pos.	5	
End	3	The sensor goes back to meas. position

Flush program: Sensor back to meas. position

Steps	Time till next step	Remark
Water	5	

H2O + Service Pos.	40	
Wait	2	
Water	60	
Air	5	
Water	10	
H2O + Meas. Pos.	5	
End	3	The sensor goes back to meas. position

Flush program with back pressure: Sensor stays in service position

Steps	Time till next step	Remark
Water	5	
H2O + Service Pos.	5	
Water	40	
Wait	2	
Water	60	Must be adapted to application properties
Air	5	
Water	10	
H2O + Meas. Pos.	5	

Wait	600	Adjust the time depending on the meas. cycle
Service position	5	
Water	40	
Wait	2	
Water	60	
Air	5	
Water	10	
End	3	The sensor stays in service position

Cleaning program: Sensor stays in service position

Steps	Time till next step	Remark
Measure position	5	
Wait	600	Adjust the time depending on the meas. cycle
Service position	5	
Water	60	
Air	5	

Cleaner	4	Must be adapted to installation
Wait	120	
Water	30	
Wait	3	
End	3	The sensor stays in service position

Cleaning program with back pressure: Sensor stays in service.

Position

Steps	Time till next step	Remark
Measure position	5	
Wait	600	Adjust the time depending on the meas. cycle
Water	5	
H2O + Service Pos.	60	
Air	5	
Cleaner	4	Must be adapted to installation
Wait	120	
Water	60	

11.2 Programs pH glass and pH Isfet calibration

11.2.1 Validation buffer 1 program with sensor staying in service position

Validation buffer 1 program with back pressure: Sensor stays in service position

Steps	Time till next step	Remark
Water	30	
H2O + Service Pos.	60	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	
Buffer 1 end	0	
Meas. E+H 7.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	60	
End	3	

Validation buffer 1: Sensor stays in service position

Steps	Time till next step	Remark
Service position	5	
Water	30	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	
Buffer 1 end	0	
Meas. E+H 7.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	30	
End	3	

11.2.2 Validation buffer 1 program with sensor back to measurement position

Validation buffer 1 program: Sensor back in meas. position

Steps	Time till next step	Remark
Service position	5	
Water	30	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	
Buffer 1 end	0	
Meas. E+H 7.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	30	
Wait	3	
Measure position	5	
End	3	

Validation buffer 1 program with back pressure: Sensor back in meas. position

Steps	Time till next step	Remark
Water	30	
H2O + Service Pos.	60	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	
Buffer 1 end	0	
Meas. E+H 7.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	60	
H2O + Meas. Pos.	5	
End	3	

11.2.3 Validation buffer 2 program with sensor staying in service position

Validation buffer 2 program with back pressure: Sensor stays in service position

Steps	Time till next step	Remark
Water	30	
H2O + Service Pos.	60	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 4	3	
Wait	300	
Buffer 1 end	0	
Meas. E+H 4.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	60	
End	3	

Validation buffer 2: Sensor stays in service position

Steps	Time till next step	Remark
Service position	5	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 4	3	
Wait	300	
Buffer 1 end	0	
Meas. E+H 4.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	60	
End	3	

11.2.4 Validation buffer 2 program with sensor back to measurement position

Validation buffer 2 program: Sensor back in meas. position

Steps	Time till next step	Remark
-------	---------------------	--------

Service position	5
Water	3
Init. calibration	0
Start 1 Pt. cal pH	0
Cleaner	4
Wait	120
Air	5
Cleaning end	0
Buffer pH 4	3
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0
cal calculation	0
Init. calibration	0
Water	30
Wait	3
Measure position	5
End	3

Validation buffer 2 program with back pressure: Sensor back in meas. position

Steps	Time till next step	Remark
Water	30	
H2O + Service Pos.	60	
Init. calibration	0	
Start 1 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Air	5	
Cleaning end	0	
Buffer pH 4	3	
Wait	300	
Buffer 1 end	0	
Meas. E+H 4.00 PH	0	
cal calculation	0	
Init. calibration	0	
Water	60	
H2O + Meas. Pos.	5	
End	3	

11.2.5 2 Pt verification program with sensor staying in service position

2 Pt verification program with back pressure: Sensor stays in service position

Steps	Time till next step	Remark
Water	3	
H2O + Service Pos.	30	
fnit. calibration	0	
Start 2 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Water	60	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	
Buffer 1 end	0	
Meas. E+H 7.00 PH	0	
Water	60	
Air	5	
End	3	
Cleaning end	0	

Buffer pH 4	4
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0
cal calculation	0
Init. calibration	0
Water	60
End	3

2 Pt verification program: Sensor stays in service position

Steps	Time till next step	Remark
Service position	30	
Water	3	
Init. calibration	0	
Start 2 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Water	60	
Air	5	
Cleaning end	0	

Buffer pH 7	4
Wait	300
Buffer 1 end	0
Meas. E+H 7.00 PH	0
Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0
cal calculation	0
Init. calibration	0
Water	60
End	3

11.2.6 2 Pt verification program with sensor back to measurement position

2 Pt verification program with back pressure: Sensor back to
meas. position

Steps	Time till next step	Remark
-------	---------------------	--------

Water	3
H2O + Service Pos.	30
Init. calibration	0
Start 2 Pt. cal pH	0
Cleaner	4
Wait	120
Water	60
Air	5
Cleaning end	0
Buffer pH 7	4
Wait	300
Buffer 1 end	0
Meas. E+H 7.00 PH	0
Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0

Meas. E+H 4.00 PH	0
cal calculation	0
Init. calibration	0
Water	60
H2O + Meas. Pos.	5
End	3

2 Pt verification program: Sensor back to meas. position

Steps	Time till next step	Remark
Service position	30	
Water	3	
Init. calibration	0	
Start 2 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Water	60	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	

Buffer 1 end	0
Meas. E+H 7.00 PH	0
Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0
cal calculation	0
Init. calibration	0
Water	30
Wait	3
Measure position	5
End	3

11.2.7 2 Pt adjustment program with sensor staying in service position

2 Pt adjustment program with back pressure: Sensor stays in service position

Steps	Time till next step	Remark
-------	---------------------	--------

Water	3
H2O + Service Pos.	30
Init. calibration	0
Start 2 Pt. cal pH	0
Cleaner	4
Wait	120
Water	60
Air	5
Cleaning end	0
Buffer pH 7	4
Wait	300
Buffer 1 end	0
Meas. E+H 7.00 PH	0
Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0

Meas. E+H 4.00 0
PH

cal calculation 0

Adjust sensor 0

Close calib. 0

Water 60

End 3

2 Pt adjustment program: Sensor stays in service position

Steps	Time till next step	Remark
-------	---------------------	--------

Service position	5	
-------------------------	---	--

Water	60	
--------------	----	--

Init. calibration	0	
--------------------------	---	--

Start 2 Pt. cal pH	0	
---------------------------	---	--

Cleaner	4	
----------------	---	--

Wait	120	
-------------	-----	--

Water	60	
--------------	----	--

Air	5	
------------	---	--

Cleaning end	0	
---------------------	---	--

Buffer pH 7	4	
--------------------	---	--

Wait	300	
-------------	-----	--

Buffer 1 end	0
Meas. E+H 7.00 PH	0
Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0
cal calculation	0
Adjust sensor	0
Close calib.	0
Water	60
End	3

11.2.8 2 Pt adjustment program with sensor back to measurement position

2 Pt adjustment program with back pressure: Sensor back to meas. position

Steps	Time till next step	Remark
Water	3	

H2O + Service Pos.	30
Init. calibration	0
Start 2 Pt. cal pH	0
Cleaner	4
Wait	120
Water	60
Air	5
Cleaning end	0
Buffer pH 7	4
Wait	300
Buffer 1 end	0
Meas. E+H 7.00 PH	0
Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0

cal calculation	0
Adjust sensor	0
Close calib.	0
Water	60
H2O + Meas. Pos.	5
End	3

2 Pt adjustment program: Sensor back to meas. position

Steps	Time till next step	Remark
Service position	5	
Init. calibration	0	
Start 2 Pt. cal pH	0	
Cleaner	4	
Wait	120	
Water	60	
Air	5	
Cleaning end	0	
Buffer pH 7	4	
Wait	300	
Buffer 1 end	0	
Meas. E+H 7.00 PH	0	

Water	60
Air	5
End	3
Cleaning end	0
Buffer pH 4	4
Wait	300
Buffer 2 end	0
Meas. E+H 4.00 PH	0
cal calculation	0
Adjust sensor	0
Close calib.	0
Water	30
Wait	3
Measure position	5
End	3

11.3 Parking and regeneration pH glass and pH Isfet

Regeneration program

Steps	Time till next step	Remark
Service position	5	

Cleaning	-	Time depending on cleaning program: Program 1
Buffer pH 7	4	
End	3	

Regeneration program with back pressure

Steps	Time till next step	Remark
Water	5	
H2O + Service Pos.	5	
Cleaning	-	Time depending on cleaning program: Program 1
Buffer pH 7	4	
End	3	

11.4 Programs pH ORP calibration

**220 mV Validation with back pressure: Sensor stays in service.
position**

Steps	Time till next step	Remark
Water	5	

H2O + Service Pos.	60
Init. calibration	0
Start 1 Pt. cal ORP	0
Cleaner	4
Wait	120
Air	5
Cleaning end	0
Pump 2 Buffer 1	4
Wait	300
Buffer 1 end	0
Meas. E+H 220 mV	0
cal calculation	0
Init. calibration	0
Water	60
End	3

220 mV Validation with back pressure: Sensor stays in meas. position

Steps	Time till next step	Remark
Water	5	

H2O + Service Pos.	60
Init. calibration	0
Start 1 Pt. cal ORP	0
Cleaner	4
Wait	120
Air	5
Cleaning end	0
Pump 2 Buffer 1	4
Wait	300
Buffer 1 end	0
Meas. E+H 220 mV	0
cal calculation	0
Init. calibration	0
Water	60
H2O + Meas. Pos.	5
End	3

220 mV Validation: Sensor stays in service. position

Steps	Time till next step	Remark
Service position	5	

Water	60
Init. calibration	0
Start 1 Pt. cal ORP	0
Cleaner	4
Wait	120
Air	5
Cleaning end	0
Pump 2 Buffer 1	4
Wait	300
Buffer 1 end	0
Meas. E+H 220 mV	0
cal calculation	0
Init. calibration	0
Water	60
End	3

220 mV Validation: Sensor stays in meas. position

Steps	Time till next step	Remark
Service position	5	
Water	60	

Init. calibration	0
Start 1 Pt. cal ORP	0
Cleaner	4
Wait	120
Air	5
Cleaning end	0
Pump 2 Buffer 1	4
Wait	300
Buffer 1 end	0
Meas. E+H 220 mV	0
cal calculation	0
Init. calibration	0
Water	60
Wait	3
Measure position	5
End	3

11.5 Program with Hold function

Every program step can contain the hold functionality. The setting is done on the program step setting visualization. Navigate to Menu/Setup/Program step (NEXT/NEXT). Two default sequences HOLD ON and HOLD OFF are already save in the system and can be used an any step of a program.

Setup/Program step		CH: 1
Hold	-	
Hold behavior	 Freeze	
Fixed value	 7.00	<input type="text"/>

Menu/ 
Meas. Point
Command 
Back

13. Pic. Hold configuration view

Cleaning program with back pressure: Sensor stays in service.


Position

Steps	Time till next step	Remark
Hold ON		
Water	5	
H2O + Service Pos.	60	
Air	5	
Cleaner	4	Must be adapted to installation
Wait	120	
Water	60	
End	3	The sensor stays in service position


Cleaning program: Sensor back in meas. position

Steps	Time till next step	Remark
Hold ON	2	
Service position	5	
Water	60	
Air	5	
Cleaner	4	Must be adapted to installation
Wait	120	
Water	30	
Wait	3	
Measure position	5	
Hold OFF	2	
End	3	The sensor back goes back to meas. position

The Hold parameters “Hold behavior” and “Hold fixed value” are defined only for digital Fieldbus communication. For analog communication please set the Hold behavior on CM44 (follow the pictures below).



(First Sensor) current output setting



(Second Sensor) current output setting