


Instruction for releasing a software option FMA90

Procedure:

1. Directly at the unit

01. Open the menu System "System" --> "Software configuration" --> "Activation SW option".
02. Enter the release code of the first page.
03. Confirm the release code with Enter.
- 04: The unit will reboot.



2. Webserver access

01. Connect the device with the computer via the Webserver
02. Please start Webserver connection and establish an online
03. Select menu "System" --> "Software configuration" --> "Activation SW option".
04. Enter the release code from the first page (only possible with online parametrization)
05. Press "Return" button. The unit will reboot.