



Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

1 Type of device

- Field device / signal processing device
- Monitoring- / operation system / hand held terminal etc.
- Modem / interface

Manufacturer : Endress+Hauser
 Device : Liquiline
 Type : CM42-Oxxxxxxxxxxx (oxygen)
 Previous software version : 20.05.02

How can the previous software version number be identified:

- (a) With standard fieldbus communication
- (b) with FieldCare/DTM
- (c) Display

2 Software

New software version : 20.05.03

Description of the modification in comparison with the predecessor version:

Enhancements & Improvements:

- Diagnostic code C215 (simulation active) is set while current output simulation
- Timestamp in calibration logbook corrected
- No identical logbook entries when changing sensors
- Automatic detection of defective RTC (Real Time Clock)
- Enhanced display interface to new display electronic
- Compatibility for HART 7 prepared

3 Compatibility

Is the operating tool compatible with the installed device software?

- Yes
- No, description:

Is a software update generally recommended?

- Yes, reason:



Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

The software update can be performed by means of ...

- SystemDAT

No, reason:

Update only necessary if functional enhancements are desired

4 Instruction manual

Is a new instruction manual necessary due to the modification of the software?

- Yes
 No

Which manual corresponds to the new software:

Device	Communication options	Manual Marking
--------	-----------------------	----------------

New instruction manuals can be referred in Internet:

<http://www.endress.com> - area „DOWNLOAD“
- declaration of the device and kind of manual

5 Price

Change in price of device in comparison with the predecessor version?

- Yes, new list price and update costs (without installation) are enclosed
 No