



# Manufacturer Information

for users regarding software updates  
(following the NAMUR recommendation 53)

## 1 Type of device

- Field device / signal processing device
- Monitoring- / operation system / hand held terminal etc.
- Modem / interface

Manufacturer : Endress+Hauser Conducta GmbH+Co  
 Device : Liquiline  
 Type : CM44x  
 Previous software version : 1.03.00

How can the previous software version number be identified:

- (a) With standard HART or Profibus Communication
- (b) with FieldCare/DTM
- (c) Display

## 2 Firmware/Software

New firm-/software version : 1.03.01

Description of the modification in comparison with the predecessor version:

### Functional enhancements

- HOLD-Softkey within the measurement screen views
- HOLD during cleaning
- Reset of lamp operating hour counter at CAS51D

### Functional improvements:

- Save of the configured Nitrate measurement unit

## 3 Compatibility

Is the newly installed firmware/software compatible with the operating tools?

- Yes
- No, description:

Is a firm/software update generally recommended?

- Yes, reasons:



## Manufacturer Information

for users regarding software updates  
(following the NAMUR recommendation 53)

The firm-/software update can be performed by means of ...  
SC-card

No, reasons:

Update only necessary if functional enhancements are desired

### 4 Instruction manual

Is a new instruction manual necessary due to the modification of the firm-/software?

Yes

No

Which manual corresponds to the new firm-/software:

| Device        | Communication options | Manual         | Marking                             |
|---------------|-----------------------|----------------|-------------------------------------|
| CM442/444/448 | All                   | BA00444CEN.pdf | Liquiline Commissioning             |
|               |                       | BA00445CEN.pdf | Liquiline Maintenance & Diagnostics |
|               |                       | BA00450CEN.pdf | Liquiline Operation & Settings      |
|               |                       | BA00451CEN.pdf | Liquiline Calibration               |

The new instruction manuals can be referred in Internet:

<http://www.endress.com>

- area „DOWNLOAD“

- declaration of the device and kind of manual

### 5 Price

Change in price of device in comparison with the predecessor version?

Yes, new list price and update costs (without installation) are enclosed

No