



Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

1 Type of device

- ☒ Field device / signal processing device
- ☐ Monitoring- / operation system / hand held terminal etc.
- ☐ Modem / interface

Manufacturer : Endress+Hauser GmbH+Co.KG, 79689 Maulburg

Device : Cerabar S

Type : PMC71, PMP71, PMP75

Previous software version : V 4.00.12

How can the previous software version number be identified:

Display: During start up and in menu:
TRANSMITTERINFO/TRANSMITTERDATA
FieldCare: MANUFACTURER VIEW/OPERATING
MENU/TRANSMITTERINFO/TRANSMITTERDATA

2 Firmware / Software

New firm-/software version : V 4.01.00

Description of the modification in comparison with the predecessor version:

Upgrade with Profibus Profil 3.02 and diagnostics according to NE 107.

3 Compatibility

Is the newly installed firmware/software compatible with the operating tools?

- ☐ Yes
- ☒ No, description:

A new Fieldcare DTM is needed.

Is a firm/software update generally recommended?

- ☒ Yes, reasons:

To use the new functionality the update is needed.

The firm-/software update can be performed by means of ...

- ☐ No, reasons:



Level



Pressure



Flow



Temperature

Liquid
Analysis

Registration

Systems
Components

Services



Solutions

Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

4 Instruction manual

Is a new instruction manual necessary due to the modification of the firm-/software?

- ☒ Yes
☐ No

Which manual corresponds to the new firm-/software:

Device	Communication option	Manual	Marking
Cerabar S	Profibus PA	Cerabar S PMC71, PMP71, PMP75 Pressure device	BA00295PEN_1513.pdf

The new instruction manuals can be referred in Internet::

<http://www.endress.com> - Area „DOWNLOAD“
- Name device type and documentation type

5 Price

Change in price of device in comparison with the predecessor version?

- ☐ Yes, new list price and update costs (without installation) are enclosed
☒ No