

















Manufacturer Information

for users regarding software updates (following the NAMUR recommendation 53)

\boxtimes	Field de	evice /	signal	processing	device

☐ Monitoring-/operation system/hand held terminal etc.

☐ Modem / interface

Manufacturer : Endress+Hauser Flowtec AG

Device : Ultrasonic Flow Measuring System

Type : Prosonic Flow 90 HART (0x58)

Order code : 90***-******A, D, W

2. Software

Previous firmware version : 2.01.00 New firmware version : 2.02.00

How can the previous : • Local display

firmware version be

• Nameplate for connections

identified? • Configuration and service software e.g. FieldCare

• Handheld terminal for remote communication e.g. Field Xpert

SFX100

Description of the : modifications in comparison to the previous

comparison to the previous firmware version

• New sensor type DN15-65

New "Original factory calibration" function

3. Compatibility

Is the operating tool compatible with the installed device firmware?

M Ye

☐ No, description:

An update of the DD's (device description) is required for all operating tools in use.





















Manufacturer Information

for users regarding software updates (following the NAMUR recommendation 53)

	Is a firmware update generally recommended?						
	_	'es: Vo, reason:					
	If the additional properties are not required for the operation of the measurement system, then no firmware update is necessary.						
4.	Instru	action manual					
	Is a new instruction manual necessary due to the modification of the firmware?						
	_	res No					
	Which manual corresponds to the new firmware?						
	Devic	ce Communic	ation options Manual	Identification			
	Proso	onic Flow 90 HART	Operating Instructions	BA068D/06/en/11.04			
	The new instruction manuals can be referred in Internet: http://www.endress.com - area "DOWNLOAD" - declaration of the device and kind of manual						
5.	Price						
	$\hfill \square$ Yes, new list price and update costs (without installation) are enclosed $\hfill \square$ No						

